



SOFTWARE-DEFINED
VIDEO PLATFORM

Zixi Edge Compute (ZEC) User Guide

Software Version 16
Document Version - DOC43-715-00010
Copyright © Zixi 2023
All Rights Reserved

Legal Notice

This document contains proprietary and confidential material of Zixi LLC. Any unauthorized reproduction, use, or disclosure of this material, or any part thereof, is strictly prohibited. This document is solely for the use of Zixi employees and authorized Zixi customers.

The error recovery techniques implemented in the Zixi protocol are protected under U.S. patent 11,546,615.

The material furnished in this document is believed to be accurate and reliable. However, no responsibility is assumed by Zixi LLC. for the use of this document or any material included herein. Zixi LLC. reserves the right to make changes to this document or any material included herein at any time and without notice.

For more information visit: www.zixi.com.

Copyright © Zixi 2023 Waltham, MA U.S.A.

All Rights Reserved.

** See back for additional licensing information*

Table of Contents

Legal Notice.....	2
Introduction to Zixi Edge Compute (ZEC)	8
Main Features	8
Zixi Software-Defined Video Platform (SDVP)	10
Zixi Transport Stream Protocol	12
Supported Protocols	13
Recording Options	14
Multicast Options.....	14
Adaptive Options	14
VOD Options	14
Latency Considerations.....	14
Billing Codes.....	14
Logging in to ZEC.....	16
Activating Your License	17
Online Activation (License Key)	17
Offline Activation (License File)	18
Reloading the License	18
Upgrading the Product Version (Linux)	19
Viewing Status.....	20
General Status.....	20
Network Status	21
Viewing Current License Information	21
License Status Screen.....	22
Machine Information	23
Operating System Information	23
Network Cards (Linux only).....	24
ZEC Inputs	25
Adding Input Stream	25
Adding Pull Streams	25

Legal Notice

Main Features

Adding UDP Streams	31
Adding File Streams	36
Adding RTMP Streams	39
Adding RTSP Streams	43
Adding HLS Streams	47
Adding TS over HTTP (Pull) Streams	51
Adding TS over HTTP (Push) Streams.....	55
Adding SRT Streams	60
SRT Client Streams	64
Adding RIST Streams	68
Adding File over HTTP Streams.....	74
Adding Multiplex Streams.....	78
Viewing Existing Input Streams.....	82
Viewing Stream Statistics.....	84
Searching for Input Streams	86
ZEC Actions on Input Streams.....	86
Stopping/Starting the Input Stream	86
Editing Input Settings or Duplicating Input Streams.....	87
Deleting Input Streams from ZEC.....	87
Recording the Input Stream.....	88
Adding TR101 Analysis to the Input Stream	89
Add Output	90
Adding SRT Client Outputs.....	94
Playing Input Streams with Players.....	97
Viewing Traceroutes	98
ZEC Actions on Multiple Inputs.....	98
Starting and Stopping Multiple Input Streams	98
Deleting Multiple Input Streams.....	99
Saving Multiple Input Streams.....	99
Resetting Stats for Multiple Input Streams	99
Creating a Failover Group	100
Encrypting an Input Stream in ZEC	103

Main Features

- Decrypting an Input Stream in ZEC 104
- Demuxing an MPTS Stream 105
- Viewing TR101 Analysis 107
 - Stream Information Statistics Panel 108
 - P1/P2 Errors 112
 - Content Analysis 113
 - Enabling Content Analysis..... 114
- ZEC Outputs 115
 - Instead of manually creating an output and then connecting the output to an input, you can define output templates with rules for automatic creation of outputs with predefined settings. The template includes an Input pattern. When an input pattern matches the pattern of an incoming input stream, the output is created automatically. For more information about Output Templates, see Decrypting an Output Stream in ZEC..... 117
 - Adding Outputs 119
 - Adding UDP Outputs 119
 - Adding RTMP and RTMPS Outputs 122
 - Adding Push Outputs 126
 - Adding TCP Outputs 129
 - Adding HTTP Push Outputs 132
 - Adding AWS Outputs 136
 - Adding SRT Outputs 139
 - Adding SRT Client Outputs 141
 - Adding RIST Outputs 143
 - Viewing Existing Outputs 148
 - Stats Pane..... 149
 - Searching for Output Streams 151
 - Performing Actions on Output Streams..... 151
 - Stopping/Starting the Input Stream 151
 - Editing Output Settings or Duplicating Output Streams..... 151
 - Deleting Output Streams from ZEC..... 152
 - Switching Input 152
 - Viewing Traceroutes 152
 - Performing Actions on Multiple Outputs 154

Legal Notice

Main Features

Start and Stop Marked Individual and Multiple Outgoing Streams	154
Toggle Output Stream Records.....	154
Delete Marked Individual and Multiple Outgoing Stream	154
Save Marked Individual and Multiple Outgoing Streams.....	154
Reset Stats for Individual and Multiple Outgoing Streams	155
Decrypting an Output Stream in ZEC.....	156
Using Output Templates.....	157
Adding SRT Client Outputs.....	161
ZEC Network Bonding	164
Using Network Bonding for Hitless Failover	164
ZEC Output with Network Bonding.....	165
Adaptive Groups	166
Creating New Adaptive Groups	166
Adding Streams to Existing Adaptive Groups	169
Adaptive Groups Templates	170
Performing Actions on Adaptive Groups	174
Stopping/Starting an Adaptive Group	174
Editing an Existing Adaptive Group.....	174
Deleting an Adaptive Group	174
Record an Adaptive Group.....	175
Play Dash.....	175
Play fMP4	176
Play HLS.....	176
Set Preroll.....	178
Server Settings	179
General.....	179
Network	184
Time	186
Live Protocols.....	187
Multicast Pull Outputs	190
Zen Master	191
SSH Connections	192

Legal Notice

Main Features

Authorization	194
Logging	196
ASI	197
Reversing the directions of the ports	198
Threads.....	199
Viewing Events Log	201
Using the Matrix.....	202
Connecting Input to Output.....	202
Disconnecting Output from Input.....	203
Matrix Interface Elements	203
Changing Matrix View	204
Searching for Specific Streams.....	204
Preview Thumbnail Elements	204
Viewing Stream Details	205
Configuring Hitless Failover	207
Configuring HTTPS.....	209
Obtaining a CA-signed Certificate	209
Creating a Self-signed Certificate.....	209
Uploading the Certificate and Private Key.....	209
Configuring MultiPath TCP	211
MultiPath Modes	211
MultiPath TCP Setup	213
Using an External Storage	214

Introduction to Zixi Edge Compute (ZEC)

Zixi Edge Compute (ZEC) is an Edge video streaming system that is installed on-premises as a Zixi endpoint, replacing the Zixi Feeder (contribution) or Zixi Receiver (distribution). ZEC offers a more robust feature set and protocol support than the Zixi Feeder/Receiver. After its installation, ZEC can be configured to function as a Feeder (Contribution), as a Receiver (distribution) or as both Feeder and Receiver.

Main Features

- **Robust content delivery over IP** - communicates with a Zixi Broadcaster over UDP-based, video-optimized protocols on private and public IP networks for maximal quality at a predictable latency
- **Adaptive Bit Rate** - Dynamically adjusts stream rate to adapt to changing network conditions, using unicast or multicast, to meet specific application requirements.
- **Recording** - store streams as MPEG-TS files.
- **Time-shifting** – records the stream to delay its broadcasting.
- **Secure and rapid file transfer** – accelerated and secure file transfers delivered at wire speed and accelerated HTTP delivery including optimized playback of HLS over UDP.
- **Clustering and load balancing** – supports cluster architectures to provide continuous uptime.
- **TR-101 Transport Stream Analyzer** – MPEG-TS ETSI TR 101-290 analyzer (priorities 1 and 2)
- **Content Analysis** - analysis of the stream's audio and video content, including audio levels, audio silence detection, frozen video detection, and more.
- **Monitoring** - captures network and content specific statistical information in real-time.
- **Network bonding with hitless failover** – reunites divided streams coming from multiple network channels into a single stream, enabling simultaneous load balancing between multiple networks and ensuring high availability of the stream.
- **Hitless failover** - hitless failover for inputs enables uninterrupted streaming when switching from one source to another. Zixi's new hitless failover feature is based on the SMPTE 2022-7 standard, which specifies “seamless” or hitless failover between binary-identical streams with synchronized RTP headers.
- **PID Mapping** - PID mapping ensures that the PIDs will have the desired values when they arrive from the Source downstream to the Target. PIDs can be specified for processing by specific PID numbers or they can be identified by category or type (i.e. codec). PIDS can be also designated to be nulled or removed completely from the stream.
- **AES stream encryption and decryption** - UDP, File and RTMP input streams can be encrypted by ZEC using a fixed key (AES 128, AES 192, AES 256), which can be entered into the input settings or automatically generated. ZEC can also decrypt contribution

Main Features

streams using a matching key, or securely forward encrypted streams to another ZEC instance, without being able to see or analyze the traffic.

- **MPTS demuxing** - MPTS streams can be demuxed into single SPTS input streams for specific programs.
- **SCTE-35** - SCTE-35 markers found in the source input will be used to segment the stream and the #EXT-X-CUE-IN/#EXT-X-CUE-OUT tags will be added to the manifest.
- **Low-latency HLS** - ZEC supports low latency HLS delivery using chunked transfer encoding, which starts sending an HTTP response as chunks of data when they are ready before the complete response is available. Chunked transfer encoding can be use with transport stream (TS) segments and with fragmented MP4 (fMP4), which is also called Common Media Application Format (CMAF).

Zixi Software-Defined Video Platform (SDVP)

Zixi's proprietary Software-Defined Video Platform or SDVP is the tight integration of components that enable broadcast-quality live video workflows to be intelligently and centrally provisioned, deployed, managed, and monitored using software and integrated devices, regardless of the underlying network infrastructure. Employed by traditional broadcasters, OTT broadcast services, service providers to source, manage, and distribute live events and 24/7 live linear channels over any IP network, protocol, cloud provider, and/or edge device.

- **Protocols & Containers** – The SDVP accepts over 17 industry protocols and containers, advancing the market leading Zixi protocol while adding additional value to tangential offerings from other vendors, standards, and open-sourced initiatives. Most customers rely on the Zixi protocol for transport as it is congestion and network-aware and can dynamically adjust to varying network conditions and employ forward error correction techniques for error-free video delivery.
- **Video Solutions Stack** – Zixi's Video Solutions Stack provides essential tools and core media processing functions for broadcast-quality transport that corrects for packet loss and jitter. Patented Hitless Failover techniques provide 99.9999%+ reliable transport between sources and receivers. The Video Solutions Stack also provides broadcasters with enhanced tools to streamline workflows including protocol switching, analytics, live 4K transcoding and repackaging, recording, time shifted delivery, and auto-slating.
- **Intelligent Data Platform** – Zixi is constantly incorporating analytics, event correlation, AI and Machine Learning tools in its platform to aggregate a user's historical and real-time metadata and present it back to them to help better predict downtime, content quality, trends, and more in the form of alerts, notifications, and background monitoring.
- **ZEN Master** – With Zixi's ZEN Master control plane, cost-effectively manage and monitor complex deployments at scale and configure and orchestrate live broadcast channels across protocols and the Zixi Enabled Network. ZEN Master allows for control of the edge, network, and cloud with full telemetry visualization of network streams. It offers essential monitoring and management tools like workflow visualization, alerting, history, automation, scheduling, reporting, and root cause analysis across complex media supply chains.

Hitless Failover, Analytics, and Bonding

Users can take advantage of its Video Solutions Stack capabilities such as analytics, hitless failover and bonding across diverse ISPs to ensure high reliability and encrypt content with AES 256 encryption and DTLS for best-in-class security. The Video Solutions Stack's unique patented hitless failover techniques ensure reliability, and its robust analytics suite provides atomic-level

Introduction to Zixi Edge Compute (ZEC)

Zixi Software-Defined Video Platform (SDVP)

telemetry on stream health that allows users to address any issues impacting QoS before the consumer's QoE is affected. The analytics solution employs machine learning techniques to provide a real-time estimated PSNR (ePSNR) with no reference video required, helping the user determine if content providers are meeting SLAs for contribution stream quality.

ZEN Master Control Plane

ZEN Master integration allows remote access to the UIs of Zixi-integrated devices and software across the Zixi Enabled Network for optimal monitoring and control from one centralized control plane. With the ZEN Master control plane, users have extensive visibility into and control over workflows that go across Zixi-enabled multi-party supply chains, with the ability to leverage alerting, extensive history graphs, automated toolsets, and scheduling and reporting capabilities that abstract complexity to reduce engineering requirements and allow media organizations to leverage operational resources, providing democratized access with geographic agility.

Zixi Transport Stream Protocol

Zixi's transport stream protocol is a content and network-aware protocol that dynamically adjusts to varying network conditions and employs error correction techniques for error-free video streaming over IP. With minimum overhead to physical bandwidth, this dynamic mechanism provides low end-to-end latency, removes jitter, recovers and re-orders packets, smooths video delivery and regenerates video to its original form, all in real-time.

Zixi delivers outstanding performance (at low predictable latency), superior reliability (no packet loss) and broadcast-grade video quality (SD, HD, and UHD) with no tradeoffs to delay, resolution or stutter.

Streaming from one Zixi-enabled device/server to another Zixi-enabled device/server protects the stream from quality degradations along the path. It enables the streaming of high-quality video over any distance, while overcoming the varying network conditions of the public Internet, where the amount of network errors, packet loss, jitter and out-of-order packets fluctuate "every second".

The Zixi transport stream protocol can be also deployed on part of the path. For example, from a ZEC to a Zixi Broadcaster (Zixi protected path) and on to another ZEC and to the end user through UDP or RTMP. In this case, the path that has challenging conditions (e.g., long distance or unstable wireless conditions) will be protected by Zixi and then delivered on to the end-user on a standard UDP or RTMP protocol.

Zixi's transport stream technology includes the following features for ultimate quality and security:

- Network sensing
- Dynamic de-jitter
- MPEG specific optimizations
- Z-ARQ error recovery
- Z-FEC - Dynamic content aware forward error correction
- Active multi-path error recovery
- Adaptive bitrate over UDP, unicast or multicast
- Rate control and congestion avoidance
- 256-bit AES transport encryption

Supported Protocols

Input:

- Zixi Pull
- MPEG-TS over UDP and/or RTP
- RTMP pull
- RTMP push
- RTSP input
- RIST (TR-06-1)
- SRT

Output:

- Zixi push
- MPEG-TS over UDP and/or RTP
- RTMP and RTMPS push
- SRT
- RIST (TR-06-1)

Recording Options

Live stream inputs can be stored as MPEG-TS files to a local disk drive or mounted drive.

Multicast Options

Multicast streams can be received or be sent by the ZEC. ZEC serves as a gateway between Unicast and Multicast streams, while allowing reliable streaming over multicast.

Adaptive Options

ZEC can create an adaptive group, subsequently editing, recording, or playing it in conjunction with DASH, HLS, HDS or Zixi. You can also set a Pre-roll video/screen that will be played before the live streaming begins.

VOD Options

ZEC supports VOD (Video on Demand) playback of stored files in multiple formats such as TS, MP4, HLS, FLV.

Latency Considerations

Latency defines the delay in which the video stream will be delivered to the endpoint. This delay is essentially a buffer that is used for additional processing, thereby improving the quality of video stream. The latency should be considered based on the importance of immediacy. For example, if the video requires interaction (e.g., between a reporter in the field and an anchor in the studio), the latency should be set to a minimum so that the interaction does not suffer from any delay.

Latency can vary from tens of milliseconds to several seconds.

Zixi protocol can start providing benefit from one frame (30ms), while increasing the latency will provide more robustness for the error-recovery.

Billing Codes

Billing codes are used to identify and differentiate traffic on a ZEC. When a billing code is added to a Source or Target, Zixi can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC.

Typical use-cases for using billing codes are:

- **Differentiating Between Clients** - If you are receiving video content from different contributing clients or sending video content to multiple external organizations, you can designate distinct billing codes for each of your clients. You can then assign the client's

Billing Codes

billing code to each Source or Target associated with that client. Your organization will then be able to bill each of their clients according to their usage.

- **Charging only for Billable Usage** - When Zixi traffic is sent between distinct organizations, situations may arise in which the usage of only one of those organizations is billable. For example, if the contributor is using a Zixi Broadcaster to send outputs as if it were a ZEC, then only the receiving organization should be billed for that traffic. In that case, the receiving organization can request a billing code and assign it to their Targets. They can then ask the contributor to assign the identical billing code to each of the Sources that they are sending. In this way, Zixi will know to bill only the organization that is receiving the traffic.

Billing codes are created by Zixi personnel on the Zixi Customer Portal for a particular organization. Zixi can create multiple Billing codes for an organization, enabling them to apply different codes to different traffic. All billing codes are password protected. If you would like to use billing codes in your workflows, please discuss it with your Zixi representative.

Logging in to ZEC

➔ To log in to ZEC:

1. In your web browser, navigate to <http://localhost:4444>.
A user authentication window opens.
2. In the **User Name** field, enter '**admin**'.
3. In the **Password** field, enter '**1234**'.
4. Click **OK**.
The Broadcaster UI opens on the **Status** page.

Activating Your License

In order to start using ZEC, first activate your license. ZEC and its optional features are activated by license files. Licenses are free and have a 10-year expiration date, but you may generate new licenses whenever necessary.


Before using ZEC, and when adding optional features, **activate** the appropriate license.

Online Activation (License Key)


The following procedure requires connectivity to the Internet. If you are not able to connect, you can activate the ZEC using the procedure described in [OFFLINE ACTIVATION \(LICENSE FILE\)](#).

➔ To Activate the License online using a License Key:

1. In the **Status** page of the ZEC UI, click **Options** in the menu bar.
The drop-down menu is displayed.



2. Click **Activate License**.
3. The **Activate License** window appears.



4. In the **Key** field, enter your Activation Key.
5. Click **Activate**.
The Zixi Broadcaster is enabled.

Activating Your License


Offline Activation (License File)

Offline Activation (License File)

If you want to activate your license without an internet connection, you can upload a License File. To obtain a license file, please contact *Zixi Support* at support@zixi.com.

➔ To Load the License File:

1. In the **Status** page of the ZEC UI, click **Options** in the menu bar. The drop-down menu is displayed.




2. Click **Load License**. The directory of the local drive opens.
3. Navigate to the License File and click **Open**.
4. A prompt window instructs you to Reload the license to activate the license.
5. Click again on **Options** and select **Reload Licenses** from the dropdown menu. The ZEC is enabled.

Reloading the License

In the event that your license expires, you must re-enter a new Zixi license key.

➔ To reload the license:

1. In the **Status** page of the Zixi Broadcaster UI, click **Options** in the menu bar. The drop-down menu is displayed.



2. Click **Reload License**. The ZEC is enabled.

Upgrading the Product Version (Linux)


When a new version of ZEC becomes available, you will receive a new installation archive file (.tar.gz file) from your Zixi representative to upgrade your Zixi Broadcaster software. It is recommended to perform the installation within a "maintenance window" and notify end users that the streaming will be momentarily interrupted. The upgrade process may last a few minutes after which the streams will be automatically resumed.



Downgrading from this release to previous versions will no longer be possible through the web UI. Downgrading is still possible via the normal software installation mechanisms.

➔ To upgrade the version:

1. In the **Status** page of the ZEC UI, click **Options** in the menu bar. The drop-down menu is displayed.



2. Click **Upgrade**.
3. Select the relevant installation archive file (.tar.gz file) and click **Open**. The installation process will begin. The process may take up to a few minutes. During the process, the streams and the management UI will not be available. After the upgrade, all streams will be automatically resumed.

Viewing Status

The Status screen displays aggregated statistics on all the input and output streams and a graph representing the network utilization of active streams over time.

➔ To View the Status of the Streams:

In the ZEC Status page, the **General** area, **Network Status** area, **License Information** area, **Machine Information** area and **Operating System** area are displayed.

General Status


General	
ID	The ZEC ID number
Host ID	Displays the ID of ZEC host.
Start Time	Displays the time that the ZEC began to actively stream content.
Up Time	The duration of time that the broadcast is running.
Inputs	The number of current active inputs
Outputs	The number of current active outputs
Remote In [kbps]	The current aggregate input bitrate from remote sources – ZEC Push/Pull (in Kbps)
Local In [kbps]	The current aggregate input bitrate from local sources – UDP streams (in Kbps)
Remote Out [kbps]	The current aggregate output bitrate to remote destinations (in Kbps)
Local Out [kbps]	The current aggregate output bitrate to local destinations (in Kbps)
HTTP Out [kbps]	The current aggregate output bitrate for HTTP streams - FLV/RTMP/HLS/ MPEG-TS over HTTP (in Kbps)
Kilobytes Sent	The cumulative traffic transmitted (in Kbps)
Kilobytes Received	The cumulative traffic received (in Kbps)
RTMP Server	Active – the RTMP server is enabled (See Settings > Live Protocols > RTMP Server section) Off – the RTMP server is disabled

Viewing Status

Network Status


Network Status

The network status graph displays the total input/output bitrate during the last hour. The changes in the amplitude of both the input (gold) and output (blue) presented in 10-minute intervals.



Viewing Current License Information

You can view the current license information in the Zixi License Status section.



The section includes the following elements:

Element	Description
Output GB	The total amount of output traffic in GB per month that is allowed in the license.
Expiration	License expiration date.
Used	The actual usage this month so far in GB.

To view additional license terms and usage statistics, click the link at the bottom of the Zixi License Status section.

The License Status Screen is displayed.

Viewing Status

Viewing Current License Information

License Status Screen



The screen includes the following elements:

Element	Description
Application	The product version and license key.
Meters	<ul style="list-style-type: none">Output GB - The total amount of output traffic used in GB per month and the total amount allowed in the license.Expires - license expiration date.
Limits	License usage restrictions. Unlimited - no restrictions.
Features	List of enabled/disabled features.
Daily Usage	Daily traffic statistics. Click the Host drop-down menu to select a specific host.

Viewing Status

Machine Information

Machine Information

This pane shows information about the machine on which ZEC is installed.

Machine Information

```
System Model: Xen HVM domU
Processor Model: Intel(R) Xeon(R) CPU E5-2686 v4 @ 2.30GHz
Processors: 1
Logical Cores: 2
Installed RAM: 4 GB
GPU(s): Not Found
```

The pane includes the following data:

Parameter	Description
System Model	The model of the machine on which the ZEC is installed.
Processor Model	The model and specifications of the machine's processor.
Processors	The number of CPUs installed on this machine.
Logical Cores	The number of logical cores per processor (for each processor).
Installed RAM	The size of the RAM installed on the machine.
GPU(s)	The number of GPUs. If no GPUs - Not Found.

Operating System Information

This pane shows information about the operating system running on the machine.

OS Information

```
OS: Amazon Linux release 2 (Karoo)
Build: 4.14.88-88.73.amzn2.x86_64
Architecture: x86_64
```

The pane Includes the following data:

Parameter	Description
OS	The operating system running on the machine.

Viewing Status

Network Cards (Linux only)

Build	The operating system build (version) number.
Architecture	The system architecture of the operating system, number of bits.
Nvidia Driver	The GPU driver version.
Cuda Version	The GPU software version.

Network Cards (Linux only)

This pane shows information about the network cards running on the machine. Each line represents another network card.

Network Cards			
NIC	Link Speed	Duplex	IPs
eth0		Full	172.31.17.149

The pane Includes the following data:

Parameter	Description
NIC	The name of the Network Interface Controller (a.k.a network card).
Link Speed	The link speed capability of the network card.
Duplex	Full - full duplex Half - half duplex
IPs	The IP of the network card.

ZEC Inputs

You can add input streams to ZEC from one of the following sources:

- **Another ZEC Instance (Pull)** – ZEC can pull a stream from a Zixi Broadcaster. Since both components use the Zixi protocol, the stream can be protected by the Zixi protocol.
- **UDP streams** - the source is a UDP or RTP stream, RTP + SMPTE 2022 FEC over unicast or multicast.
- **Local files (for VOD)** – the source in this case is a local transport stream file from your local computer or local network.
- **RTMP streams** - The source is an RTMP stream, pushed into ZEC or pulled by it.
- **RTSP** - The source is an RTSP stream, pushed into ZEC, or pulled by it.
- **HLS** - The source is an HLS stream that is pulled by ZEC.
- **HTTP Pull/Push (TS over HTTP)** - The source is a Transport Stream over HTTP, which is pushed into ZEC or pulled by it.
- **RIST** – The source is a RIST stream using Simple or Main Profile over unicast or multicast.
- **SRT Caller/Push** – The source is an SRT stream and is configured via Zen Master or ZEC API only.
- **SRT Listener/Pull** – The source includes an SRT stream that is pulled by ZEC. The connection is initiated by ZEC.
- **File over HTTP** – The source is a file on an HTTP server (e.g. S3) that is copied to a temporary location on the local computer.
- **Multiplex** – Takes multiple Single Program Transport Streams and combines them into one Multi Program Transport Stream file.

ZEC does not support transcoding, WebRTC and NDI streams. In order to access these features, contact Zixi Customer Service to upgrade to Zixi Broadcaster by activating a Broadcaster license.

Adding Input Stream

ZEC enables you to add various types of streams. When you create a new stream, select the stream type and then fill in the fields that are applicable for that stream type.

Adding Pull Streams

Typically, a Pull Stream is transmitted from a Broadcaster. In this case, the stream is initiated by your ZEC.

If the stream is an MPTS stream and you want to demux it into separate SPTS input streams, create the stream, by following the instructions below, and then follow the instructions in the [Demuxing an MPTS Stream](#) section.

ZEC Inputs

Adding Input Stream

The error recovery techniques implemented in the Zixi protocol Pull streams are protected under U.S. patent 11,546,615.

➔ To Add a Pull Stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID** for ZEC.



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.



This setting can be modified without interrupting an existing stream.

5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **Pull** for the input stream.

The screenshot shows the 'Add new input stream' dialog box. At the top, there are tabs for STATUS, INPUTS, OUTPUTS, ADAPTIVE, VOD, SETTINGS, EVENT LOG, MATRIX, and a LOGOUT button. The dialog has a title bar 'Add new input stream' with a close button. Inside, there are input fields for 'Stream ID', 'Max Outputs' (set to 'Unlimited'), and a checked 'Show in Matrix' checkbox. Below these are radio buttons for input types: Pull (selected), UDP, File, RTMP, RTSP, HLS, TS over HTTP, SRT, SRT Client, RIST, WebRTC, File over HTTP, and Multiplex. A 'Stream parameters' section includes fields for Host, Port (2088), Stream, Password, Latency [ms] (4000), Ignore TLS certificate errors (unchecked), and Bind to IP (Any). There are also checkboxes for Billing Codes, Enable multicast on pull outputs, Decrypt stream, Enable encryption, and Recording parameters. 'Ok' and 'Cancel' buttons are at the bottom right.


7. Specify the **Stream Parameters** (see Input Stream Parameter table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
10. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Input Stream Parameter Table below. For more information, see [Decrypting an Input Stream in ZEC](#).

ZEC Inputs

Adding Input Stream




11. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
12. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
13. Click **OK**. The “Input added” message appears on the top of the screen. The Pull Stream is added to ZEC and now appears in the list of streams available in ZEC inputs UI.

Input Stream Parameters table

Parameter	Description
Stream Parameters	The general stream settings.
Host	Enter the IP Address of the remote ZEC server. Note that additional (failover) destinations can be added by clicking the adjacent “+” button
Port	Enter the port through which ZEC receives the stream from another ZEC server. Default: 2088 The default input port for ZEC is UDP port 2088 . This port <i>must be open</i> on any firewalls between ZEC and other devices it is communicating with.
Stream	Enter the unique stream ID from another ZEC server.
Password (Optional)	If desired, enter the string for authentication. It must be identical to the string configured on the other ZEC.
Latency [ms]	Specify the maximum number of milliseconds that ZEC should protect the stream for. For example, 6000 milliseconds would ensure that the stream is protected for up to six seconds of delay in the network. This setting affects memory usage as higher levels of protection require more buffering. Default:6000.
Ignore TLS certificate error	Select this option when connecting to a trusted server that does not have a valid certificate. When this option is selected, ZEC will ignore the TLS certificate errors.  This setting can be modified without interrupting an existing stream.
Bind to IP	Select from the drop-down list the local IP address to be used for this Input, OR select <i>Any</i> to enable any IP to be used.

ZEC Inputs

Adding Input Stream

Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, Zixi can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by Zixi personnel on the Zixi Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings .  This setting can be modified without interrupting an existing stream.
Multicast-Only (for multicast enabled)	If desired, specify multicast-only outputs.
Decrypt stream	Select this checkbox to decrypt the Input stream. Please note that the stream will not be encrypted as it passes through the ZEC path. For more information, see Decrypting an Input Stream in ZEC .
Decryption type (for Decrypt stream enabled)	Specify the type of encryption that is being used in the stream.  This setting can be modified without interrupting an existing stream.
Decryption key (for Decrypt stream enabled)	Specify the key for decryption.  This setting can be modified without interrupting an existing stream.
Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.

ZEC Inputs

Adding Input Stream

Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	<p>Select the radio button for the desired storage type and then fill in the relevant parameters.</p> <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.• Record to S3 – the file is saved to your AWS S3 Bucket.
Record to Disk Parameters	<p>Specify the file name pattern that Zixi will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time - mandatory• %U=YYYYmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
Keep recorded files for [hours]	Specify the maximum time for storing the recording. Default: 0 hours
Custom Path	Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the Settings > General screen.
Record to S3 Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time - mandatory• %U=YYYYmmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

Adding UDP Streams

This enables ZEC to receive a UDP stream. The UDP stream is not protected by the Zixi protocol. The UDP streams can be one of the following types:

- **UDP** – the input stream is plain UDP.
- **RTP** – the input stream uses the RTP protocol, which adds RTP headers to the UDP stream. RTP adds a 12-byte header, which includes a sequence number and a timestamp that can be used to detect dropped packets. The sequence number in the RTP headers can be used to do automatic reordering and the timestamps can help overcome inter-packet gaps, also known as IAT (Inter Arrival Time). However, plain RTP does not feature error recovery or error protection. By default, the RTP headers (which include the timestamps and sequences) are being used on the input side, but then they are stripped off and they no longer propagate to outputs.
- **RTP + SMPTE 2022 FEC** – the input stream includes forward error correction, which enables error recovery or error protection.

If the stream is an MPTS stream and you want to demux it into separate SPTS input streams, create the stream, by following the instructions below, and then follow the instruction in the [Demuxing an MPTS Stream](#) section.

➔ To Add a UDP Stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID**.



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.

ZEC Inputs

Adding Input Stream

6. Select **UDP** for the input stream.

The screenshot shows the 'Add new input stream' dialog box. At the top, there are tabs for STATUS, INPUTS, OUTPUTS, ADAPTIVE, VOD, SETTINGS, EVENT LOG, MATRIX, and LOGOUT. The dialog has a title bar 'Add new input stream' with a close button. Below the title bar, there are fields for 'Stream ID:', 'Max Outputs: Unlimited', and 'Show in Matrix: '. A row of radio buttons allows selecting an input protocol: Pull, UDP (selected), File, RTMP, RTSP, HLS, TS over HTTP, SRT, SRT Client, RIST, WebRTC, File over HTTP, and Multiplex. The 'Stream parameters' section includes: Port, Multicast IP, SSM source IP, Type (dropdown menu with 'UDP' selected), Bind to IP (dropdown menu with 'Any' selected), Max Bitrate [kbps]: 8000, and De jitter Buffer [ms]: 0. Below this are checkboxes for 'Billing Codes', 'Enable multicast on pull outputs', and 'Enable encryption'. The 'Recording parameters' section is checked and includes radio buttons for 'Record to disk' (selected) and 'Record to S3'. It also has a 'File name template:' field with the value '%S_%Y%M%D-%T.ts' and a legend below it: '%S=stream id; %Y=year; %M=month; %D=day; %T=HH.MM.SS creation time; %U=YYYYmmdTHHMMSSZ UTC timestamp'. There are also two time input fields: 'Max recorded file duration [HH:MM]:' with '02:00' and 'Keep recorded files for [HH:MM]:' with '00:00'. A 'Custom path:' field is empty. At the bottom right are 'Ok' and 'Cancel' buttons.

7. Specify the **Stream Parameters** (see Input Stream Parameters Table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
10. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
11. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
12. Click **OK**.

The “Input added” message appears on the top of the screen. The UDP Stream is added to ZEC and now appears in the list of streams available in the ZEC inputs UI.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	The general stream settings.
Port	Specify the port to listen on. This port must be open on all firewalls between ZEC and other devices it is communicating with.

ZEC Inputs

Adding Input Stream

Multicast IP	If multicast, type the Multicast IP address (or leave blank in the case of Unicast).
SSM Source	Specify the source IP for a source-specific multicast.
Type	<p>Select the appropriate protocol type from the drop-down list:</p> <p>UDP – the input stream is plain UDP.</p> <p>RTP – the input stream uses the RTP protocol, which adds RTP headers to the UDP stream. RTP adds a 12-byte header, which includes a sequence number and a timestamp that can be used to detect dropped packets. The sequence number in the RTP headers can be used to do automatic reordering and the timestamps can help overcome inter-packet gaps, also known as IAT (Inter Arrival Time).</p> <p>However, plain RTP does not feature error recovery or error protection. By default, the RTP headers (which include the timestamps and sequences) are being used on the input side, but then they are stripped off and they no longer propagate to outputs.</p> <p>RTP + SMPTE 2022 FEC – the input stream includes forward error correction, which enables error recovery or error protection.</p>
Bind to IP	Select from the drop-down list the local IP address to be used for this Input, OR select <i>Any</i> to enable any IP to be used.
Max. bitrate [kbps]	<p>Specify the maximum expected bitrate for memory allocation. Recommended: 2X the actual bitrate, which will prevent buffer overruns (especially with VBR streams). Default: 8000.</p> <p>Note – Overflows will typically occur when the Max Bitrate isn't sufficient.</p>
Dejitter Buffer [ms]	<p>A buffer size used to de-jitter RTP and UDP inputs. For RTP packet timing is fixed according to packet arrival times and RTP timestamps. For UDP dejittering is only based on arrival times. Default: 0.</p> <p>Assuming that the timestamps in the RTP are accurate, this feature is helpful when the encoder generates an accurate timestamp on the stream, but the arrival is jittery/bursty. In case of jitter, specify a higher value than the RTP input jitter. To view the Jitter level of the input stream, create the input and select it on the Inputs screen, the Jitter metric will be displayed in the Stats pane at the bottom of the screen.</p>
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, Zixi can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by Zixi personnel on the Zixi Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from ZEC.
Billing password	Enter the password that corresponds to this billing code.

ZEC Inputs

Adding Input Stream

Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default, ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.
Multicast-Only (for multicast enabled)	Selecting this checkbox will force the transmission of this stream only in multicast.
Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	Select the radio button for the desired storage type and then fill in the relevant parameters. <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.• Record to S3 – the file is saved to your AWS S3 Bucket.
Record to Disk Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id – optional.• %Y=year – optional• %M=month – optional• %D=day – optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmdTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
Keep recorded files for [hours]	Specify the maximum time for storing the recording. Default: 0 hours
Custom Path	Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the Settings > General screen.
Record to S3 Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id – optional.• %Y=year – optional• %M=month – optional• %D=day – optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

Adding File Streams

This input creates a file input for the ZEC from a local or mounted disk and subsequently streams it to the end-user.

If the stream is an MPTS stream, you can either upload it as an MPTS file or you can demux it into separate SPTS input streams. To Demux the MPTS stream, create the input stream by following the instructions below, and then follow the instruction in the Demuxing an MPTS Stream section.

➔ To Add a File Stream:

1. In the ZEC Navigation menu, click the Inputs tab.
2. In the Menu bar, click New Input. The Add a new input stream window is displayed.
3. Enter the unique Stream ID.

ZEC Inputs

Adding Input Stream



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **File** for the input stream.

7. Specify the **Stream Parameters** (see Input Stream Parameter table).
8. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
9. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
10. Click **OK**. The “Input added” message appears on the top of the screen. The Push Stream is added to ZEC and now appears in the list of streams available in the ZEC inputs UI.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	
Path	Type the local or mounted (Linux) disk or click the adjacent browse button to select the desired one. The suffix .ts indicates a transmitted stream.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream’s outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default, ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.

ZEC Inputs

Adding Input Stream

Multicast Only (for Multicast enabled) If desired, specify multicast only outputs.

Enable Encryption Select this checkbox to encrypt the Input stream. For more information, see see [Encrypting an Input Stream in ZEC](#).

Encryption type (for Encryption enabled) Specify the type of Encryption (AES 128/192/256).

Encryption key (for encryption enabled) Click **Generate** to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.

Adding RTMP Streams

This enables you to create a Push or Pull RTMP input stream.

➔ To Add a RTMP Stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID**.



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **RTMP** for the input stream.

The screenshot shows the 'Add new input stream' dialog box. At the top, there are tabs for STATUS, INPUTS, OUTPUTS, ADAPTIVE, VOD, SETTINGS, EVENT LOG, MATRIX, and LOGOUT. Below the tabs, there's a sub-tab 'Enable multicast pool to use this feature'. The main form has the following fields and options:

- Stream ID: [Text input field]
- Max Outputs: [Unlimited]
- Show in Matrix:
- Input Type: Pull, UDP, File, RTMP, RTSP, HLS, TS over HTTP, SRT, SRT Client, RIST, WebRTC, File over HTTP, Multiplex
- Stream parameters:
 - Type: Push, Pull
 - Bind to IP: [Any]
 - Disconnect if inactive:
 - Muxing Bitrate [kbps]: [0]
 - Smoothing Latency [ms]: [0]
- Billing Codes:
- Enable multicast on pull outputs:
- Enable encryption:
- Recording parameters:
- Buttons: [Ok] [Cancel]

7. Specify the **Stream Parameters** (see Input Stream Parameters Table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
10. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
11. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).

ZEC Inputs

Adding Input Stream

- Click **OK**. The “Input added” message appears on the top of the screen. The RTMP Stream is added to ZEC and now appears in the list of streams available in the ZEC inputs UI.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	The general stream settings.
Type	Select the desired type for the RTMP stream: <ul style="list-style-type: none">Push – the stream is pushed to ZEC (not initiated by the ZEC). No additional connection parameters need to be filled. If the stream name will match, the stream will be inputted.Pull – ZEC will initiate the stream by accessing it through the following parameters:
URL (for Pull)	Type the Stream URL from which ZEC will access. Use the following URL format: <code>rtmp://host:[port]/app/stream.</code> You can define RTMPS clients with the proven security of a secure socket layer (SSL), by using the <code>rtmps:// url</code>
Stream Name (for Pull)	Type the unique name for the stream that has been defined in the RTMP server.
User Name (for Pull)	Specify the user name to authenticate on the remote RTMP server
Password (for Pull)	Specify the string that is used for authorization on the remote RTMP server.
Ignore TLS certificate	Select this option when connecting to a trusted server that does not have a valid certificate. When this option is selected, ZEC will ignore the TLS certificate errors.
Disconnect if inactive	Disconnects the connection if inactive.
Padding	If the stream's bitrate fluctuates you can pad the stream with null packets to create a steady bitrate. Select this checkbox to enable padding.
Muxing bitrate (for Padding enabled)	Specify the padding level in kbps.

ZEC Inputs

Adding Input Stream

Smoothing Latency [ms]	The Smoothing feature uses a buffer to time packets according to the stream's clock. This is useful when there are bursts in the rate in which the stream arrives. The smoothing features creates a queue in the buffer, allowing smoother entry into ZEC. The Smoothing parameter defines the size of the buffer in Milliseconds. A larger buffer enables smoother entry, however, it may influence the latency rate.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default, ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.
Multicast Only (for Multicast enabled)	Select the check box to force only Multicast outputs.
Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	Select the radio button for the desired storage type and then fill in the relevant parameters. Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section. <ul style="list-style-type: none">• Record to S3 – the file is saved to your AWS S3 Bucket.
Record to Disk Parameters	
File Name Template	Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated. The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these

ZEC Inputs

Adding Input Stream

variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:

- %S=stream id - optional.
- %Y=year - optional
- %M=month - optional
- %D=day - optional
- %T=HH.MM.SS creation time – mandatory
- %U=YYYYmmddTHHMMSSZ UTC timestamp – optional

For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.

Max recorded

file duration [hours] Specify the maximum time allotted for recording a video stream. Default: 2 hours

Keep recorded files for [hours]

Specify the maximum time for storing the recording. Default: 0 hours

Custom Path

Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the **Settings > General** screen.

Record to S3 Parameters

Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.

The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:

File Name Template

- %S=stream id - optional.
- %Y=year - optional
- %M=month - optional
- %D=day - optional
- %T=HH.MM.SS creation time – mandatory
- %U=YYYYmmddTHHMMSSZ UTC timestamp – optional

For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.

ZEC Inputs

Adding Input Stream

Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

Adding RTSP Streams

This enables you to create RTSP streams.

➔ To Add RTSP Streams:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.

The screenshot shows the 'Add new input stream' dialog box. At the top, there are navigation tabs: STATUS, INPUTS, OUTPUTS, ADAPTIVE, VOD, SETTINGS, EVENT LOG, MATRIX, and LOGOUT. The dialog has a title bar 'Add new input stream' with a close button. Below the title bar, there are input fields for 'Stream ID:' and 'Max Outputs:' (set to 'Unlimited'). A 'Show in Matrix:' checkbox is checked. A row of radio buttons allows selecting the input type: Pull, UDP, File, RTMP, RTSP (selected), HLS, TS over HTTP, SRT, SRT Client, RIST, WebRTC, File over HTTP, and Multiplex. Under 'Stream parameters', there are fields for 'URL (rtsp://host:[port]/stream):' (with 'rtsp://localhost:554/' entered), 'Video UDP port:' (5000), 'Audio UDP port:' (5002), 'Pad to bitrate [kbps]:' (0), and 'Smoothing Latency [ms]:' (0). A 'TCP:' checkbox is checked. Below these are four unchecked checkboxes: 'Billing Codes', 'Enable multicast on pull outputs', 'Enable encryption', and 'Recording parameters'. At the bottom right, there are 'Ok' and 'Cancel' buttons.

3. Enter the unique **Stream ID**.



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

ZEC Inputs

Adding Input Stream

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **RTMP** for the input stream.
7. Specify the **Stream Parameters** (see Input Stream Parameters Table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
10. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
11. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
12. Click **OK**. The “Input added” message appears on the top of the screen. The RTSP Stream is added to ZEC and now appears in the list of streams available in the ZEC inputs UI.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	The general stream settings.
URL	Type the Stream URL from which ZEC will access.
Video UDP Port	Specify the UDP port to be used for streaming the video.
Audio UDP Port	Specify the UDP port to be used for streaming the audio.
Pad to bitrate [kbps]	If the stream's bitrate fluctuates you can pad the stream with null packets to create a steady bitrate. This setting determines the padding level in kbps.
Smoothing to Latency [ms]	Specify the maximum latency you can tolerate for the stream in milliseconds. Recommended - the length of two frames.
TCP	Select this checkbox for streams that use TCP protocol. Leave unselected in case the stream uses UDP.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.
Multicast Only (for Multicast enabled)	Select the check box to force only Multicast outputs.

ZEC Inputs

Adding Input Stream

Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	<p>Select the radio button for the desired storage type and then fill in the relevant parameters.</p> <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.• Record to S3 – the file is saved to your AWS S3 Bucket.
Record to Disk Parameters	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmdTTHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
File Name Template	
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours

ZEC Inputs

Adding Input Stream

Keep recorded files for [hours]	Specify the maximum time for storing the recording. Default: 0 hours
Custom Path	Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the Settings > General screen.
Record to S3 Parameters	
File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmdTTHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

ZEC Inputs

Adding Input Stream

Adding HLS Streams

This screen enables ZEC to receive an HLS stream. The HLS stream is not protected by the Zixi protocol. There are two options for pulling the stream:

- **Single source (adaptive bitrate)** - the stream can be an adaptive bitrate stream. In this case, ZEC will pull the main playlist to adapt between bitrates according to network conditions.
- **Multiple sources** - it is possible to pull multiple input streams with static individual bitrates. In this case, ZEC will automatically create a separate input for each bitrate.

➔ To Add an HLS stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID**.



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Enter the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **HLS** for the input stream.

The screenshot shows the 'Add new input stream' dialog box. The 'Stream ID' field is empty. 'Max Outputs' is set to 'Unlimited' and 'Show in Matrix' is checked. Under 'Pull' options, 'HLS' is selected. The 'Stream parameters' section shows 'Master playlist URL' as 'http://localhost:7777/input.m3u8', 'Download type' as 'Multiple sources (pull all bitrates)', and 'Buffering Time [ms]' as '30000'. Other options like 'Inject SCTE35 on CUE marks', 'Support EXT-X-DATERANGE', 'Start from last segment', 'Zixi broadcaster', and 'Use HTTP parameters for substreams' are unchecked. There are also sections for 'Billing Codes', 'Enable multicast on pull outputs', 'Enable encryption', and 'Recording parameters', all with unchecked checkboxes. 'Ok' and 'Cancel' buttons are at the bottom right.

7. Specify the **Stream Parameters** (see Input Stream Parameters Table below).

ZEC Inputs

Adding Input Stream

8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
10. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
11. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
12. Click **OK**.

The “Input added” message appears on the top of the screen. The HLS stream is added to ZEC and now appears in the list of streams available in the ZEC inputs UI. If the "multiple sources" option was select, ZEC will automatically create a separate input for each bitrate.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	The general stream settings.
Master Playlist URL	Specify the URL of the HLS stream.
Download Type	Specify whether the variants will be pulled from a single source (adaptive bitrate) or multiple sources (pull all bitrates).
Inject SCTE35 on CUE Marks	Select this checkbox to inject SCTE markers into the adaptive stream manifest. SCTE-35 markers found in the source input will be used to segment the stream and the #EXT-X-CUE-IN/#EXT-X-CUE-OUT tags will be added to the manifest.
Support EXT-X-DATERANGE	EXT-X-DATERANGE is a way of providing timed metadata in an HLS manifest. It is used to define date range metadata in a media playlist. A possible use case is defining timed metadata for interstitial regions such as advertisements, but can be used to define any timed metadata needed by your stream. Select this checkbox to enable this feature.
Start from last segment	Select this checkbox to begin downloading from the last segment in the playlist. By selecting this mode, you may lose the previous data in the playlist (i.e., the chunks before the last chunks will not be downloaded), but latency will be lowered.
Zixi broadcaster	Select this checkbox if you are pulling the HLS from a Zixi Broadcaster. This will add a parameter in the request to pull the stream so that the origin Zixi Broadcaster can identify the puller and show a single output in the outputs table. If you don't select this option, the origin Zixi Broadcaster will display a different output for each downloaded segment.

ZEC Inputs

Adding Input Stream

Use HTTP parameters for substreams	Select this checkbox to use HTTP parameters for substreams. If your Master URL has HTTP parameters (e.g., <code>http://server.com/main.m3u8?user=someuser&password=somepass&etc=...</code>), the parameters will be propagated as subplaylists and chunks. For example, the master playlist will have a subplaylist: <code>sub_playlist1.m3u8</code> In this case, the request for this playlist will be: <code>http://server.com/sub_playlist1.m3u8?user=someuser&password=somepass&etc=...</code>
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default, ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.
Multicast Only (for Multicast enabled)	If desired, specify multicast only outputs.
Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	Select the radio button for the desired storage type and then fill in the relevant parameters. <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.• Record to S3 – the file is saved to your AWS S3 Bucket.
Record to Disk Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmdTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
Keep recorded files for [hours]	Specify the maximum time for storing the recording. Default: 0 hours
Custom Path	Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the Settings > General screen.
Record to S3 Parameters	
File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional

ZEC Inputs

Adding Input Stream

- %M=month - optional
- %D=day - optional
- %T=HH.MM.SS creation time – mandatory
- %U=YYYYmmdTHHMMSSZ UTC timestamp – optional

For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.

Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
---	--

URL	Specify the URL of the S3 bucket.
------------	-----------------------------------

Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
--------------------------------------	--

Access Key	The access key that is used for accessing the S3 bucket.
-------------------	--

Secret Key	The secret key that is used for accessing the S3 bucket.
-------------------	--

Adding TS over HTTP (Pull) Streams

In this mode ZEC pulls a Transport Stream over TCP from an HTTP server. In this case, the stream is initiated by your ZEC.

➔ To Add a TS over HTTP (Pull) Stream:

1. In the ZEC navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID**.



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **TS over HTTP** for the input stream.
7. In the **Type** field, select **Pull**.

ZEC Inputs

Adding Input Stream

The screenshot shows the 'Add new input stream' dialog box. At the top, there are tabs for STATUS, INPUTS, OUTPUTS, ADAPTIVE, VOD, SETTINGS, EVENT LOG, MATRIX, and LOGOUT. The dialog has a title bar 'Add new input stream' with a close button. Below the title bar, there are input fields for 'Stream ID:', 'Max Outputs:' (set to 'Unlimited'), and 'Show in Matrix:' (checked). A row of radio buttons allows selecting the input type: Pull, UDP, File, RTMP, RTSP, HLS, TS over HTTP (selected), SRT, SRT Client, RIST, WebRTC, File over HTTP, and Multiplex. Under the 'Stream parameters' section, there are radio buttons for 'Type:' (Push/Pull), a text field for 'URL (http://host:[port]/stream):' containing 'http://localhost:7777/input.ts', and a text field for 'Smoothing [ms]:' containing '1000'. Below these are four checkboxes: 'Billing Codes', 'Enable multicast on pull outputs', 'Enable encryption', and 'Recording parameters'. At the bottom right, there are 'Ok' and 'Cancel' buttons.

8. Specify the **Stream Parameters** (see Input Stream Parameter table).
9. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
10. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
11. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
12. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
13. Click **OK**.

The “Input added” message appears on the top of the screen. The TS over HTTP stream is added to ZEC and now appears in the list of streams available in the ZEC inputs UI.

Input Stream Parameters table

Parameter	Description
Stream Parameters	The general stream settings.
TS URL	Enter the URL of the Transport Stream.
Smoothing	The Smoothing feature uses a buffer to time packets according to the stream's clock. This is useful when there are bursts in the rate in which the stream arrives. The smoothing features creates a queue in the buffer, allowing smoother entry into ZEC. The Smoothing parameter defines the size of the buffer in Milliseconds. A larger the buffer enables smoother entry. However, it may influence the latency rate.

ZEC Inputs

Adding Input Stream

Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default, ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings .
Multicast-Only (for multicast enabled)	If desired, specify multicast-only outputs.
Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	Select the radio button for the desired storage type and then fill in the relevant parameters. <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.• Record to S3 – the file is saved to your AWS S3 Bucket.
Record to Disk Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
Keep recorded files for [hours]	Specify the maximum time for storing the recording. Default: 0 hours
Custom Path	Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the Settings > General screen.
Record to S3 Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

Adding TS over HTTP (Push) Streams

In this mode ZEC will receive a Transport Stream over TCP from an HTTP server. In this case, the stream is initiated by the source HTTP Server, while ZEC remains in “listening mode” until the stream (with the specified stream ID) is initiated.

➔ To Add a TS over HTTP (Push) Stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the **Menu** bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID** for ZEC.

ZEC Inputs

Adding Input Stream



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **TS over HTTP** for the input stream
7. In the **Type** field, select **Push**.

Stream ID	Max Outputs	Show in Matrix	Type	Smoothing [ms]	User	Password	Billing Codes	Transmit as multicast	Enable encryption	Recording parameters
	Unlimited	<input checked="" type="checkbox"/>	Push	1000			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Stream ID	Stream Name	IP	Port	Time	Off	None	1
rtmp-pull	rtmp_pull	172.31.35.41	4131	11:12:48	Off	None	1

8. Specify the **Stream Parameters** (see Input Stream Parameters Table below).
9. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
10. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
11. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
12. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
13. Click **OK**.

The “Input added” message appears on the top of the screen. The TS over HTTP stream is added to ZEC and now appears in the list of streams available in the ZEC inputs UI.

ZEC Inputs

Adding Input Stream

Input Stream Parameters Table

Parameter	Description
Stream Parameters	The general stream settings.
Smoothing	The Smoothing feature uses a buffer to time packets according to the stream's clock. This is useful when there are bursts in the rate in which the stream arrives. The smoothing features creates a queue in the buffer, allowing smoother entry into ZEC. The Smoothing parameter defines the size of the buffer in Milliseconds. A larger buffer enables smoother entry, however, it may influence the latency rate.
User	If the stream is password protected, enter the username to access the stream.
Password	If the stream is password protected, enter the password.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default, ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings .
Multicast Only	Selecting this checkbox will force the transmission of this stream only in multicast.
Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	Select the radio button for the desired storage type and then fill in the relevant parameters. <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.• Record to S3 – the file is saved to your AWS S3 Bucket.
Record to Disk Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
Keep recorded files for [hours]	Specify the maximum time for storing the recording. Default: 0 hours
Custom Path	Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the Settings > General screen.

ZEC Inputs

Adding Input Stream

Record to S3 Parameters

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

Adding SRT Streams

SRT (Secure Reliable Transport) is an open-source video streaming protocol that brings pristine quality, low-latency live video over the public internet. This input enables the ZEC to receive an SRT stream. The source of the stream is an SRT client that pushes the stream into ZEC. The connection is initiated by the source SRT client, which connects to the Listening Port on the ZEC. The connection can be password protected.

More details about SRT can be found at <https://www.haivision.com/products/srt-secure-reliable-transport/>

➔ To Add a SRT Stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the **Menu** bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID** for ZEC.



Note this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **SRT** for the input stream.

The screenshot shows the 'Add new input stream' dialog box. At the top, there are navigation tabs: STATUS, INPUTS, OUTPUTS, ADAPTIVE, VOD, SETTINGS, EVENT LOG, MATRIX, and a LOGOUT button. The dialog has a title bar 'Add new input stream' with a close button. The 'Stream ID' field is empty. 'Max Outputs' is set to 'Unlimited'. 'Show in Matrix' is checked. Below this, there are radio buttons for different protocols: Pull, UDP, File, RTMP, RTSP, HLS, TS over HTTP, SRT (selected), SRT Client, RIST, WebRTC, File over HTTP, and Multiplex. Under 'Stream parameters', there are input fields for 'Listening Port', 'Password[10-80]', 'Latency[ms]' (set to 1000), 'Max Bitrate[kbps]' (set to 10000), and a dropdown for 'Bind to IP' (set to 'Any'). There are also checkboxes for 'Billing Codes', 'Enable multicast on pull outputs', 'Enable encryption', and 'Recording parameters'. At the bottom right, there are 'Ok' and 'Cancel' buttons.

7. Specify the **Stream Parameters** (see Input Stream Parameters Table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).

ZEC Inputs

Adding Input Stream

10. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
11. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
12. Click **OK**.
The “Input added” message appears on the top of the screen. The SRT Stream is added to ZEC and now appears in the list of streams available in the ZEC inputs UI.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	
Listening Port	Specify the port to listen on. This port must be open on all firewalls between ZEC and other devices it is communicating with.
Password	If the stream is password protected, enter the password.
Latency	Specify the maximum latency of the stream in milliseconds. Default: 1000
Max. bitrate [kbps]	Specify the maximum expected bitrate for memory allocation. Recommended: 2X the actual bitrate, which will prevent buffer overruns (especially with VBR streams). Default: 10000. Note – Overflows will typically occur when the Max Bitrate isn't sufficient.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, Zixi can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by Zixi personnel on the Zixi Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from ZEC.
Billing password	Enter the password that corresponds to this billing code.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A Zixi receiver that will pull the stream will receive it in multicast. By default ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.
Multicast-Only (for multicast enabled)	Selecting this checkbox will force the transmission of this stream only in multicast.

ZEC Inputs

Adding Input Stream

Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	<p>Select the radio button for the desired storage type and then fill in the relevant parameters.</p> <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.• Record to S3 – the file is saved to your AWS S3 Bucket. The mechanism uses AWS multipart upload. Amazon advises to define a lifetime rule for objects on destination bucket.
Record to Disk Parameters	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>

ZEC Inputs

Adding Input Stream

Max recorded file duration [HH:MM] Specify the maximum time allotted for recording a video stream. Default: 2 hours

Keep recorded files for [HH:MM] Specify the maximum time for storing the recording. Default: 0 hours

Custom Path Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the **Settings > General** screen.

Record to S3 Parameters

Specify the file name pattern that Zixi will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.

The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:

File Name Template

- %S=stream id – optional.
- %Y=year – optional
- %M=month – optional
- %D=day – optional
- %T=HH.MM.SS creation time – mandatory
- %U=YYYYmddTHMMSSZ UTC timestamp – optional

For example, the following pattern %Y_recording%T.ts will generate the following file name 2017_recording15:32:35.ts.

Max recorded file duration [HH:MM] Specify the maximum time allotted for recording a video stream. Default: 2 hours

URL Specify the URL of the S3 bucket.

Ignore TLS certificate errors TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.

Access Key The access key that is used for accessing the S3 bucket.

Secret Key The secret key that is used for accessing the S3 bucket.

ZEC Inputs

Adding Input Stream

SRT Client Streams

SRT (Secure Reliable Transport) is an open-source video streaming protocol that brings pristine quality, low-latency live video over the public internet. This input enables the ZEC to pull an SRT stream from the source. The connection is initiated by ZEC. The connection can be password protected.

More details about SRT can be found at <https://www.haivision.com/products/srt-secure-reliable-transport/>

➔ To Add an SRT Client Stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID**.



Note this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **SRT Client** for the input stream.

The screenshot shows the 'Add new input stream' dialog box. At the top, there are navigation tabs: STATUS, INPUTS, OUTPUTS, ADAPTIVE, VOD, SETTINGS, EVENT LOG, MATRIX, and LOGOUT. The dialog box has a title bar 'Add new input stream' and a close button. It contains the following fields and options:

- Stream ID: [Text input field]
- Max Outputs: [Unlimited] (drop-down menu)
- Show in Matrix:
- Input type selection: Pull , UDP , File , RTMP , RTSP , HLS , TS over HTTP , SRT , SRT Client , RIST , WebRTC , File over HTTP , Multiplex
- Stream parameters section:
 - Host: [Text input field]
 - Port: [Text input field]
 - Password[10-80]: [Text input field]
 - Latency[ms]: [1000] (drop-down menu)
 - Max Bitrate[kbps]: [10000] (drop-down menu)
 - Bind to IP: [Any] (drop-down menu)
- Billing Codes
- Enable multicast on pull outputs
- Enable encryption
- Recording parameters

At the bottom right, there are 'Ok' and 'Cancel' buttons.

7. Specify the **Stream Parameters** (see Input Stream Parameters Table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).

ZEC Inputs

Adding Input Stream

10. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
11. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
12. Click **OK**.
The “Input added” message appears on the top of the screen. The SRT Client Stream is added to the ZEC and now appears in the list of streams available in the ZEC inputs UI.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	
Host	Enter the IP Address of the remote server from which the SRT stream will be pulled.
Port	Enter the port through which the ZEC receives the stream from another server.
Password	If the stream is password protected, enter the password.
Latency	Specify the maximum latency of the stream in milliseconds. Default: 1000
Max. bitrate [kbps]	Specify the maximum expected bitrate for memory allocation. Recommended: 2X the actual bitrate, which will prevent buffer overruns (especially with VBR streams). Default: 10000. Note – Overflows will typically occur when the Max Bitrate isn't sufficient.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, Zixi can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by Zixi personnel on the Zixi Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from ZEC.
Billing password	Enter the password that corresponds to this billing code.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default, ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.

ZEC Inputs

Adding Input Stream

Multicast-Only (for multicast enabled) Selecting this checkbox will force the transmission of this stream only in multicast.

Enable Encryption Select this checkbox to encrypt the Input stream. For more information, see [Encrypting an Input Stream in ZEC](#). **Encrypting an Input Stream in**

Encryption type (for Encryption enabled) Specify the type of Encryption (AES 128/192/256).

Encryption key (for Encryption enabled) Click **Generate** to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.

Recording parameters Select this checkbox to customize the recording parameters.

Select the radio button for the desired storage type and then fill in the relevant parameters.

- Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.
- Record to S3 – the file is saved to your AWS S3 Bucket. The mechanism uses AWS multipart upload. Amazon advises to define a lifetime rule for objects on destination bucket.

Record to Disk Parameters

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that Zixi will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmddTHHMMSSZ UTC timestamp - optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2017_recording15:32:35.ts.</p>
Max recorded file duration [HH:MM]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
Keep recorded files for [HH:MM]	Specify the maximum time for storing the recording. Default: 0 hours
Custom Path	Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the Settings > General screen.
Record to S3 Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [HH:MM]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

Adding RIST Streams

This enables ZEC to receive a RIST stream. RIST seeks to provide reliable, high performance media transport by using UDP at the transport layer to avoid the inefficiencies of TCP, then layering on top Forward Error Correction and Retransmits to add the reliability inherently absent from UDP. ZEC supports RIST streams from any compliant RIST device.

ZEC supports the following RIST profiles:

- **Simple Profile** - The RIST Simple Profile provides best-in-class packet protection, as well as support for multi-link bonding and seamless switching.
- **Main Profile** – The RIST Main Profile builds upon the features of the Simple Profile to provide backwards compatibility, while opening the door for additional features, including the use of industry-standard DTLS with a variety of available cyphers to ensure

ZEC Inputs

Adding Input Stream

the most up-to-date protection, while being flexible to accommodate local legal regulations. Support for pre-shared keys is also included, which makes RIST Main Profile compatible with one-to-many environments such as satellite or multicast distribution

Contact your ZEC representative to learn more about interoperability testing between ZEC and 3rd party devices. More details about RIST can be found at www.rist.tv

➔ To Add a RIST Stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID**.



Note this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **RIST** for the input stream.

The screenshot shows the 'Add new input stream' dialog box. At the top, there are tabs for STATUS, INPUTS, OUTPUTS, ADAPTIVE, VOD, SETTINGS, EVENT LOG, MATRIX, and LOGOUT. The dialog box has a title bar 'Add new input stream' and a close button. Below the title bar, there are input fields for 'Stream ID', 'Max Outputs' (set to 'Unlimited'), and 'Show in Matrix' (checked). A row of radio buttons allows selecting an input protocol: Pull, UDP, File, RTMP, RTSP, HLS, TS over HTTP, SRT, SRT Client, RIST (selected), WebRTC, File over HTTP, and Multiplex. Below this, there are sections for 'Stream parameters', 'Billing Codes', 'Enable multicast on pull outputs', 'Enable encryption', and 'Recording parameters'. The 'Stream parameters' section includes: Profile (Simple Profile), Local Port, Multicast IP, SSM source IP, Remote Port (0=auto) (0), Type (RTP), Bind to IP (Any), Max Bitrate (8000), and Max Latency (1000). At the bottom right, there are 'Ok' and 'Cancel' buttons.

7. Specify the **Stream Parameters** (see Input Stream Parameters Table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).

ZEC Inputs

Adding Input Stream

10. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
11. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
12. Click **OK**.
The “Input added” message appears on the top of the screen. The RIST Stream f is added to the ZEC and now appears in the list of streams available in the ZEC inputs UI.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	The general stream settings.
Profile	Select one of the following RIST profiles that matches the input stream: <ul style="list-style-type: none">• Simple Profile (default)• Main Profile
Simple Profile Parameters	
Local Port	Specify the port to listen on. This port must be open on all firewalls between the ZEC and other devices it is communicating with.
Multicast IP	If multicast, type the Multicast IP address (or leave blank in the case of Unicast).
SSM Source	Specify the source IP for a source-specific multicast.
Remote Port	Specify the remote port in the source RIST device. Default: 0 (any port)
Type	Select one of the following protocol types from the drop-down list: <ul style="list-style-type: none">• RTP• RTP + SMPTE 2022 FEC
Bind to IP	Select from the drop-down list the local IP address to be used for this Input, OR select <i>Any</i> to enable any IP to be used.
Max. bitrate [kbps]	Specify the maximum expected bitrate for memory allocation. Recommended: 2X the actual bitrate, which will prevent buffer overruns (especially with VBR streams). Default: 8000. Note – Overflows will typically occur when the Max Bitrate isn't sufficient.
Max Latency [ms]	Specify the maximum latency of the stream in milliseconds. Default: 1000
Main Profile – Push Parameters	

ZEC Inputs

Adding Input Stream

Local Port	Specify the port to listen on. This port must be open on all firewalls between the ZEC and other devices it is communicating with.
Multicast IP	If multicast, type the Multicast IP address (or leave blank in the case of Unicast).
SSM Source	Specify the source IP for a source-specific multicast.
Remote Port	Specify the remote port in the source RIST device. Default: 0 (any port)
Type	Select one of the following protocol types from the drop-down list: <ul style="list-style-type: none">• RTP• RTP + SMPTE 2022 FEC
Bind to IP	Select from the drop-down list the local IP address to be used for this Input, OR select <i>Any</i> to enable any IP to be used.
Max. bitrate [kbps]	Specify the maximum expected bitrate for memory allocation. Recommended: 2X the actual bitrate, which will prevent buffer overruns (especially with VBR streams). Default: 8000. Note – Overflows will typically occur when the Max Bitrate isn't sufficient.
Max Latency [ms]	Specify the maximum latency of the stream in milliseconds. Default: 1000
Use DTLS	Select this checkbox to encrypt the stream dynamically using DTLS.
Main Profile – Pull Parameters	
Remote Host	Specify the IP Address of the remote RIST device from which the stream will be pulled.
Remote Port	Specify the port of the remote RIST device from which the stream will be pulled. Default: 0 (any port)
Local Port	Specify the local port to which the stream will be pulled. Default: 0 (any port)
Type	Select one of the following protocol types from the drop-down list: <ul style="list-style-type: none">• RTP• RTP + SMPTE 2022 FEC
Bind to IP	Select from the drop-down list the local IP address to be used for this Input, OR select <i>Any</i> to enable any IP to be used.
Max. bitrate [kbps]	Specify the maximum expected bitrate for memory allocation. Recommended: 2X the actual bitrate, which will prevent buffer overruns (especially with VBR streams). Default: 8000. Note – Overflows will typically occur when the Max Bitrate isn't sufficient.
Max Latency [ms]	Specify the maximum latency of the stream in milliseconds. Default: 1000.

ZEC Inputs

Adding Input Stream

Use DTLS	Select this checkbox to encrypt the stream dynamically using DTLS.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.
Multicast-Only (for multicast enabled)	Selecting this checkbox will force the transmission of this stream only in multicast.
Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	Select the radio button for the desired storage type and then fill in the relevant parameters. <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.• Record to S3 – the file is saved to your AWS S3 Bucket.
Record to Disk Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmddTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
Keep recorded files for [hours]	Specify the maximum time for storing the recording. Default: 0 hours
Custom Path	Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the Settings > General screen.
Record to S3 Parameters	

ZEC Inputs

Adding Input Stream

File Name Template	<p>Specify the file name pattern that ZEC will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">• %S=stream id - optional.• %Y=year - optional• %M=month - optional• %D=day - optional• %T=HH.MM.SS creation time – mandatory• %U=YYYYmmdTHHMMSSZ UTC timestamp – optional <p>For example, the following pattern %Y_recording%T.ts will generate the following file name 2022_recording15:32:35.ts.</p>
Max recorded file duration [hours]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

Adding File over HTTP Streams

This enables you to add a File over HTTP stream, where the source is a file on an HTTP server (e.g. S3) that is copied to a temporary location on the local computer.

➔ To Add File over HTTP Stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID**.



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.

ZEC Inputs

Adding Input Stream

5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
6. Select **File over HTTP** for the input stream.

The screenshot shows the 'Add new input stream' dialog box. It includes a title bar with 'Add new input stream' and a close button. The main area contains the following elements:

- Stream ID:
- Max Outputs:
- Show in Matrix:
- Stream type selection: Pull, UDP, File, RTMP, RTSP, HLS, TS over HTTP, SRT, SRT Client, RIST, File over HTTP, Multiplex
- Stream parameters: URL:
- Billing Codes:
- Enable multicast on pull outputs:
- Enable encryption:
- Recording parameters:
- Buttons:

7. Specify the **Stream Parameters** (see Input Stream Parameter table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
10. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
11. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
12. Click **OK**. The “Input added” message appears on the top of the screen. The WebRTC stream is added to the ZEC and now appears in the list of streams available in ZEC inputs UI.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	The general stream settings.
URL	Specify the URL for the File over HTTP stream.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, Zixi can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by Zixi personnel on the Zixi Customer Portal for a particular organization.

ZEC Inputs

Adding Input Stream

Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.
Multicast Only (for Multicast enabled)	Select the check box to force only Multicast outputs.
Enable Encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	Select the radio button for the desired storage type and then fill in the relevant parameters. <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.• Record to S3 – the file is saved to your AWS S3 Bucket. The mechanism uses AWS multipart upload. Amazon advises to define a lifetime rule for objects on destination bucket.
Record to Disk Parameters	
File Name Template	Specify the file name pattern that Zixi will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated. The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:

ZEC Inputs

Adding Input Stream

- %S=stream id - optional.
- %Y=year - optional
- %M=month - optional
- %D=day - optional
- %T=HH.MM.SS creation time – mandatory
- %U=YYYYmddTHHMMSSZ UTC timestamp - optional

For example, the following pattern %Y_recording%T.ts will generate the following file name 2017_recording15:32:35.ts.

Max recorded file duration [HH:MM]

Specify the maximum time allotted for recording a video stream. Default: 2 hours

Keep recorded files for [HH:MM]

Specify the maximum time for storing the recording. Default: 0 hours

Custom Path

Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the **Settings > General** screen.

Record to S3 Parameters

File Name Template

Specify the file name pattern that Zixi will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.

The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:

- %S=stream id - optional.
- %Y=year - optional
- %M=month - optional
- %D=day - optional
- %T=HH.MM.SS creation time – mandatory
- %U=YYYYmddTHHMMSSZ UTC timestamp - optional

For example, the following pattern %Y_recording%T.ts will generate the following file name 2017_recording15:32:35.ts.

ZEC Inputs

Adding Input Stream

Max recorded file duration [HH:MM]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

Adding Multiplex Streams

This enables you to combine multiple SPTS streams into a single Multiplex stream.

➔ To Add a Multiplex Stream:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. In the Menu bar, click **New Input**. The **Add a new input stream** window is displayed.
3. Enter the unique **Stream ID**.



Note: this must be identical (case sensitive) to the stream name configured in the sending Zixi Broadcaster or MediaConnect.

4. Select the maximum concurrent connections to this stream from the **Max. Outputs** drop-down list. Default: Unlimited.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.

Adding Input Stream

6. Select **Multiplex** for the input stream.

7. Specify the **Stream Parameters** (see Input Stream Parameter table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Input Stream Parameter Table below).
9. If you want to **Enable multicast on pull outputs**, select this checkbox (see Input Stream Parameter table).
10. If you want to **Enable encryption**, select this checkbox (see Input Stream Parameters Table). For more information, see [Encrypting an Input Stream in ZEC](#).
11. If you want to configure the **Recording Parameters**, specify them in the respective fields (see Input Stream Parameter table).
12. Click **OK**. The “Input added” message appears on the top of the screen. The Multiplex stream is added to the ZEC and now appears in the list of streams available in ZEC inputs UI. The created mpts file is accessible in the **File** tab at the top of the ZEC administrative screen and can be added as a new File input stream in the **Add a new input stream** window.

Input Stream Parameters Table

Parameter	Description
Stream Parameters	The general stream settings.
Target bitrate [kbps]	Specify the target bitrate for the multiplex stream. The target bitrate number should be at least as high as the sum of all of the effective bitrates of the individual STPS inputs included in the multiplex stream.
Inputs	Click <input type="button" value="+"/> to add a stream.
Stream	Select a stream ID from the drop-down list.

ZEC Inputs

Adding Input Stream

Program Name	Enter a Program Name for the SPTS stream. This overwrites any pre-existing Program Name previously assigned to the stream.
Program Number	Enter a Program Number for the SPTS stream. This overwrites any pre-existing Program Number previously assigned to the stream.
Base PID	Enter a Base PID number for the STPS stream. Zixi will automatically assign new PID numbers for all PIDs based on this number. Each Input's Base PID should be separated by an interval greater than 10.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, Zixi can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by Zixi personnel on the Zixi Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable multicast on pull outputs	Select this checkbox to enable the transmission of this stream's outputs as multicast. A ZEC that will pull the stream will receive it in multicast. By default ZEC is configured to allow transparent fallback to unicast if it is out of the LAN. Requires enabling Multicast Pull in the Settings.
Multicast Only (for Multicast enabled)	Select the check box to force only Multicast outputs.
Enable encryption	Select this checkbox to encrypt the Input stream. For more information, see Encrypting an Input Stream in ZEC .
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256).
Encryption key (for Encryption enabled)	Click Generate to generate an encryption key. The generated encryption key must be sent to the end-user to decipher the received encoded stream.
Recording parameters	Select this checkbox to customize the recording parameters.
Destination Type	Select the radio button for the desired storage type and then fill in the relevant parameters. <ul style="list-style-type: none">• Record to disk – the recording is saved on the local disk. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see Using an External Storage section.

ZEC Inputs

Adding Input Stream

- **Record to S3** – the file is saved to your AWS S3 Bucket. The mechanism uses AWS multipart upload. Amazon advises to define a lifetime rule for objects on destination bucket.
-

Record to Disk Parameters

File Name Template

Specify the file name pattern that Zixi will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.

The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:

- %S=stream id - optional.
- %Y=year - optional
- %M=month - optional
- %D=day - optional
- %T=HH.MM.SS creation time – mandatory
- %U=YYYYmmddTHHMMSSZ UTC timestamp - optional

For example, the following pattern %Y_recording%T.ts will generate the following file name 2017_recording15:32:35.ts.

Max recorded file duration [HH:MM]

Specify the maximum time allotted for recording a video stream. Default: 2 hours

Keep recorded files for [HH:MM]

Specify the maximum time for storing the recording. Default: 0 hours

Custom Path

Optionally specify a storage location for the recorded files that is relative to the root folder. This location bypasses the location specified as the root folder in the **Settings > General** screen.

Record to S3 Parameters

File Name Template

Specify the file name pattern that Zixi will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.

The file name pattern can include any string and up to five variables listed below. Only the %T=HH.MM.SS creation time is mandatory. You can change the order of

ZEC Inputs

Viewing Existing Input Streams

these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:

- %S=stream id - optional.
- %Y=year - optional
- %M=month - optional
- %D=day - optional
- %T=HH.MM.SS creation time – mandatory
- %U=YYYYmddTHHMMSSZ UTC timestamp - optional

For example, the following pattern %Y_recording%T.ts will generate the following file name 2017_recording15:32:35.ts.

Max recorded file duration [HH:MM]	Specify the maximum time allotted for recording a video stream. Default: 2 hours
URL	Specify the URL of the S3 bucket.
Ignore TLS certificate errors	TLS certificate for S3 bucket might be detected as faulty if bucket name contains dot[s]. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access Key	The access key that is used for accessing the S3 bucket.
Secret Key	The secret key that is used for accessing the S3 bucket.

Viewing Existing Input Streams

The **Inputs** screen displays all the input streams that have been created. At the bottom of the screen you can also view accumulative utilization statistics for any connected streams selected. Hovering the cursor on the status indicator of a stream will provide you with the stream configuration information and basic utilization statistics, where applicable.

ZEC Inputs

Viewing Existing Input Streams

QA-Elena-SRT-1-2p2n

Version 15.1.44030 Linux 64-bit CPU: 7.11% Disk: 49.47% Mem: 19.24% Clock: 21:07:26

STATUS INPUTS OUTPUTS ADAPTIVE VOD SETTINGS EVENT LOG MATRIX LOGOUT

Inputs Search Inputs [x] [refresh] [help]

Status	ID	Type	Source	Bitrate[kbps]	Up Time	TR 101 290	Error	Outputs	Actions
Connected	auto-created-push	Push	172.31.35.41	2469	04:00:10	Off	None	0	[stop] [refresh]
Connected	dup	Push	172.31.35.41	2422	04:00:08	Off	None	0	[stop] [refresh]
Connected	file	File	Chubchub.ts	989	11:21:20	Off	None	1	[stop] [refresh]
Offline	hls-nonZixi	HLS		0	00:00:00	Off	Stopped	0	[stop] [refresh]
Connected	hls_4088	HLS	http://172.31.35.41:7777/hls-group/bbb.m3u8?hlsid=HTTP_ID_0	3139	11:21:20	Off	None	1	[stop] [refresh]
Connected	pull	Pull	172.31.35.41:2088	2425	11:19:53	Off	None	13	[stop] [refresh]
Connected	pushToZec	* Push	172.31.35.41	1955	04:00:10	Off	None	0	[stop] [refresh]
Connected	rist-main-pull	RIST Pull	172.31.35.41:4060	2910	11:20:15	Off	None	1	[stop] [refresh]
Connected	rist-main-push	RIST(main)	172.31.35.41:46419	2030	11:20:15	Off	None	1	[stop] [refresh]
Connected	rist-simple	RIST	172.31.35.41:4020	1980	11:21:20	Off	None	1	[stop] [refresh]
Connected	rtmp-pull	rtmp_pull	172.31.35.41	2162	11:21:20	Off	None	1	[stop] [refresh]
Connected	rtmp-push	* rtmp_push	172.31.35.41	2164	11:19:41	Off	None	1	[stop] [refresh]
Connected	rtp	RTP	172.31.35.41:4090	3124	11:21:20	Off	None	1	[stop] [refresh]
Offline	rtsp	RTSP		0	00:00:00	Off	Stopped	0	[stop] [refresh]
Connected	srt-pull	SRT-CLIENT	172.31.35.41:4000	2339	11:19:50	Off	None	1	[stop] [refresh]
Connected	srt-push	SRT	172.31.35.41:4010	2339	11:19:55	Off	None	1	[stop] [refresh]
Connected	ts-over-http	HTTP	http://172.31.35.41:7777/bbb.ts	2589	11:19:40	Off	None	1	[stop] [refresh]
Connected	udp	UDP	172.31.35.41:4080	2798	11:21:20	Off	None	1	[stop] [refresh]

Statistics

Bitrate [kbps] [Link](#): Total Packets [Link](#):
 Last Connected: [Link](#): Packet Rate [Link](#):
 Reconnections [Link](#): Overflows [Link](#):

Any of the columns in the following table can be sorted in ascending/descending order by clicking on its heading. The Search text box in the upper left-hand side of the screen can be used to search for a specific input stream by entering the desired Stream ID.

Field	Description
Status	<p>Displays the status of input stream. The following colored indicators are displayed:</p> <ul style="list-style-type: none"> Green = Connected Yellow = Connecting Red = Disconnected with an error condition Blue = Offline with no connection attempts Grey = Offline and stopped

ZEC Inputs

Viewing Stream Statistics

ID	Displays the unique ID of the stream, as defined in ZEC.
Type	Displays the type of input stream.
Source	Displays the source host and port number.
Bitrate [kbps]	Displays bitrate of the connected input stream.
Up Time	Displays the amount of time the stream has been active.
TR 101 209	Displays if the Analyzer is active and the streams that are being analyzed according to the TR101 protocol. P1 and P2 are error priorities.
Error	Displays connection and transmission errors.
Outputs	Displays the amount of outputs currently configured for this input stream.
Actions	Provides access to various actions to be performed on this input stream (see ZEC Actions on Input Streams).

Viewing Stream Statistics

You can view all the accumulative statistics for a connected input stream in real-time. It is possible to reset the counters by clicking **Reset**. The statistics may differ between the various stream types.

➔ To View Stream Statistics:

1. On the Inputs page of ZEC, click the desired input stream for which you want to view statistics for. The stream's statistics are displayed on the bottom of the screen.

Field	Description
Bitrate (kbps)	Displays the current bitrate of the input stream.
Last Connected	Displays the date and time in which the stream was connected.
Up Time	Displays the amount of time the stream has been active.
Reconnections	Displays the number of reconnection attempts.
Total Packets	Displays the total number of packets that have been transmitted.
Packet Rate	Displays the current number of packets per second.

ZEC Inputs

Viewing Stream Statistics

Remuxing Resets	Remuxing resets can occur when remuxing to CBR (i.e value of 'Remux to bitrate' field is set). In this case, the value is not high enough to remux the video+audio+other PIDs data. A possible solution is to increase value of the 'Remux to bitrate' parameter.
Remuxing Overflows	This indicates that the multiplexer internal queues are full.
Smoothing Drops	The Smoothing feature uses a buffer to time packets according to the stream's clock. This is useful when there are bursts in the rate in which the stream arrives. The smoothing drops indicator indicates that the stream is too "bursty".
RTT (ms)	Displays the Round Trip Time (RTT) from the source (in milliseconds).
Jitter (ms)	Displays the current Jitter, measured in milliseconds.
Latency (ms)	Displays the stream latency configured on the source.
Congestion [%]	Displays an estimation of the communication's congestion level – '0' means congestion free, '100' means fully congested.
Total Packets	Displays the total number of packets that have been transmitted.
Packet Rate	Displays the current number of packets per second.
Packet Loss %	Displays current percentage of the packets that were dropped on route from the source.
Dropped Packets	Displays the total number of packets dropped between the source and ZEC since the beginning of the stream.
Recovered Packets	Displays the number of dropped packets that have been recovered since the beginning of the stream.
Not Recovered Packets	Displays the number of non-recovered packets.
FEC Packets	Displays the number of FEC packets transmitted.
FEC Recovered	Displays the number of FEC packets recovered.
ARQ Requests	Displays the number of requests for retransmission of dropped packets made with ARQ.
ARQ Recovered	Displays the number of dropped packets recovered via ARQ.
ARQ Duplicates	Displays the number of duplicate recovery packets received via ARQ.
ARQ Out of Credit	Displays the number of retransmission requests skipped because it hits a limit, which protects from floods of retransmissions when many packets are missing.


ZEC Inputs

Searching for Input Streams

Overflows	The number of packets lost due to buffer overflow. Note: Overflow is usually the result of the Max Bitrate being too low.
Consecutive Not Recovered	Displays the maximal number of consecutive "not recovered packets" in the last measurement period (1 second). This measurement this can help identify long streaks of unrecovered packets, which it is not possible to see by just looking at the global "not recovered" counter.

Searching for Input Streams

➔ To Search for an Input Stream:

1. In the **Inputs** page of ZEC, type in the specific input stream name in the search text box on the left-hand top of the screen and click .
2. The **Input** screen displays the requested output stream(s).

ZEC Actions on Input Streams


Every stream has a shortcut button that can be used to perform relevant actions on the stream. The following actions can be performed through the Actions button:

- Adding Analysis to the Input Stream
- Recording the Input Stream
- Stopping/Starting the Input Stream
- Deleting Input Streams from ZEC
- Editing Input Settings or Duplicating Input Streams
- Playing Input Streams with Players
- Add Output
- Traceroute

Stopping/Starting the Input Stream


You can start or stop the input stream at any time.

➔ To Stop/Start the Input Stream:


1. On the Inputs page of ZEC, click the desired row of the input stream that you want to stop.
2. Click the  button on the right end of the selected row and then **Stop**. The selected row which was a Connected Input Stream is no longer displayed and appears below as **Offline**.
To continue the Input Stream click **Start** from the same menu.

Editing Input Settings or Duplicating Input Streams

➔ To Edit the Configuration of an Input Stream:


1. In the ZEC **Inputs** page, click the desired input stream that you want to edit.
2. Click  button on the right end of the selected row and then **Edit**. The Edit input stream name window is displayed. You can modify any of the settings.
3. Click **OK**. The new settings will take effect.


➔ To Duplicate the Configuration of an Input Stream:

1. In ZEC **Inputs** page, click the desired input stream that you want to duplicate.
2. Click  button on the right end of the selected row and then **Duplicate**. The **Duplicate input stream name** window with the settings of the original input stream is displayed. You can modify any of these settings.
3. Click **OK**. The duplicate input stream with its new settings will be created.

Deleting Input Streams from ZEC

➔ To Delete an Input Stream from ZEC:

1. In the ZEC **Inputs** page, click the desired input stream that you want to delete.
2. Click the  button on the right end of the selected row and then **Delete**. The message "Are you sure you want to delete input?" is displayed.




3. Click **OK**. The selected row which was a Connected Input Stream will be deleted.

Recording the Input Stream

You can record an input stream and store it as .TS file. The duration of the time the recording will be kept on the server is defined in the Input Stream configuration. It is possible to record to an external destination by replacing the default storage location with a symbolic link. To learn more, see [Using an External Storage](#) section.



➔ To Record the Input Stream:


1. In the ZEC **Inputs** page, click the desired input stream that you want to record.
2. Click the  button on the selected row and then choose **Record**. A small red dot appears in the green circle at the left-hand side of the selected row indicating that the input stream is being recorded.
3. Clicking **Stop Recording** will stop the recording of the Input Stream.
Recorded files can be found in the Zixi install directory in the following path:
<Zixi install directory>/files













Adding TR101 Analysis to the Input Stream

A TR101 analysis can be added to the input stream for the monitoring of the TS while in operation. The analysis can be used to check the integrity of the TS and the most important elements of the stream. The analysis includes priority 1 and 2. To learn more about TR101 analysis see [TR 101 290 Technical Report](#). For more information on ZEC's TR101 analysis, see [Viewing TR101 Analysis](#).

➔ To Add Analysis to the Input Stream:

1. In the ZEC **Inputs** page, click the stream you want to analyze from the input streams UI.
2. Click the  button on the right end of the selected row and then select **Analyze**. The statuses of a **P1** (high priority error) and **P2** (low priority error) are indicated by an adjacent green or red button displayed in the TR 101 290 column. You can view the detailed analysis of the P1 and P2 errors by clicking on the stethoscope icon  shown in the **TR 101 290** column. The **Stream Analysis** screen is displayed.



Indicator	#Errors	Last error	Error message
Priority 1			
 TS_sync_loss	0	--	--
 Sync_byte_error	0	--	--
 PAT_error	0	--	--
 Continuity_count_error	0	--	--
 PMT_error	0	--	--
 PID_error	0	--	--
Priority 2			
 Transport_error	0	--	--
 CRC_error	0	--	--
 PCR_error	0	--	--
 PCR_accuracy_error	372	2022-Oct-30 13:05:41	PCR accuracy of selected program is not within 500ns. (2.58864e+07ns) PID:256
 PTS_error	0	--	--
 CAT_error	0	--	--
Content analysis			

3. On the left-hand side of the screen is a stream information tree that displays accumulative statistics regarding the stream. Click the + icons to expand the tree. The following can be done from the Stream Analysis screen:
 - **Content Analysis** – shows errors in the audio and video content (i.e. Frozen video, Blank picture, Silent audio, Low video quality and Audio clipping).
 - **Refresh** – refreshes the data that is displayed.

ZEC Inputs

ZEC Actions on Input Streams

- **Reset** – resets all the field's values to zero.
 - **Close** – closes the **Stream Analysis** screen.
4. Clicking Stop Analysis will discontinue the action.

Add Output


This is an alternative method (shortcut) to adding an output to a specific input stream instead of configuring it through the **Outputs** screen. The available types of outputs are:


- **UDP** – Target is a UDP or RTP stream, over unicast or multicast.
- **RTMP** – Real Time Messaging Protocol streams can be played on systems that accept this protocol as input. Originally designed to enable Adobe® Flash® streams to be sent between a server and a client, RTMP has become a popular protocol for streaming into content-delivery networks (CDNs).
- **Pull** – Pull streams are Zixi protocol streams destined for ZEC. In this case, the ZEC can offer status and statistics for a stream that is being pulled from it by another device.
- **Push** – Push streams are Zixi protocol streams destined for other ZEC instances.
- **TCP** – The TCP output can push the stream directly to a TCP socket or to an HTTP server.
- **HTTP Push** – The HTTP Push output stream can be encapsulated in HLS or DASH. The source of the output stream is a predefined adaptive group that has been configured in the **Adaptive Groups** screen. The configuration of the stream includes the option to delete outdated stream fragments on the server. Output streams can be pushed to one ZEC instance.
- **AWS** – The HTTP output stream (HLS or DASH) can be pushed to an AWS S3 Bucket or too an Elemental MediStore. The native S3 support includes the ability to configure the S3 authentication credential, including the Region, Access Key, and Secret Key.
- **SRT Caller/Push** – The SRT stream is pushed to an SRT-compatible target. The connection is initiated by ZEC.
- **SRT Listener/Pull** – The SRT stream is pulled from the ZEC by an SRT Client. The connection is initiated by the target SRT client.
- **RIST** – The RIST output stream can be pushed to an external target using Simple or Main Profile over unicast or multicast. The output stream can include Forward Error Correction (SMPTE-2022 FEC).

ZEC Inputs

ZEC Actions on Input Streams

➔ To Add Output:

1. In the ZEC Navigation menu, click the **Inputs** tab.
2. Click the Settings button , and then click **New Output**. The **New Output** window with the settings of the selected output stream is displayed.



3. Follow the specific instructions of each output type from one of the following sections:
 - **Adding UDP Outputs**
 - **Adding RTMP and RTMPS Outputs**
 - **Adding Push Outputs**
 - **Adding TCP Outputs**
 - **Adding HTTP Push Outputs**
 - **Adding AWS Outputs**
 - **Adding SRT Outputs**

ZEC Inputs


ZEC Actions on Input Streams

The SRT output can be pulled to/from an SRT-enabled device and is configured via Zen Master or Zixi API only. SRT stands for 'Secure Reliable Transport' and is an open-source video transport protocol and technology stack. SRT uses secure streams and easy firewall traversal to optimize streaming performance and deliver high-quality video over even the most unreliable networks.

The other connection on the stream must be connected to Zixi Broadcaster or AWS MediaConnect.

➔ To Create an SRT Output:

1. In the ZEC **Outputs** page, click **+ New Output**. The **New Output** window is displayed.



2. Type in the unique identifier for this output in the **Output Name**.
3. Select an **Input Stream** to be made available on this output from the drop-down list.
4. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
5. Select **SRT**.
6. Enter the **Output Parameters** (see Output Stream Parameters Table).
7. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameters Table below).
8. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see Decrypting an Output Stream in ZEC.
9. Click **OK**.

The new SRT Output with its settings is created and now appears on the screen.

ZEC Inputs

ZEC Actions on Input Streams

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Listening Port	Specify the port to listen on. This port must be open on all firewalls between the ZEC and other devices it is communicating with.
Password	If the stream is password protected, enter the password.
Latency	Specify the maximum latency of the stream in milliseconds. Default: 1000
Encryption Type	Specify the type of Encryption (AES 128/192/256).
Bind to IP	Select from the drop-down list the local IP address to be used for this output, OR select <i>Any</i> to enable any IP to be used.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable Decryption	Select this checkbox to decrypt an encrypted stream.
Decryption type	<p>If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used.</p> <p>Select Automatic to decrypt a stream that has been encrypted using Automatic encryption.</p> <p>Only if the stream has not been encrypted, select None (default).</p> <p>Important Notice: if the stream has been encrypted you must decrypt it in the output.</p>
Decryption key	If the decryption type includes a key, enter the key to decrypt the stream during output.

Adding SRT Client Outputs

The SRT Client output can be pushed to an SRT-enabled device and is configured via Zen Master or Zixi API only. SRT stands for ‘Secure Reliable Transport’ and is an open-source video transport protocol and technology stack. SRT uses secure streams and easy firewall traversal to optimize streaming performance and deliver high-quality video over even the most unreliable networks.

➔ To Create an SRT Client Output:

1. In the ZEC **Outputs** page, click **+ New Output**. The **New Output** window is displayed.

The screenshot shows the 'New output' configuration window. The window title is 'New output'. It has a purple header with tabs: OUTPUTS, ADAPTIVE, VOD, SETTINGS, EVENT LOG, MATRIX. The 'New output' dialog contains the following fields and options:

- Output Name: [Text input field]
- Input Stream: [Dropdown menu]
- Show in Matrix:
- Output Protocol Selection: UDP , RTMP , Push , TCP , HTTP Push , AWS , SRT , SRT Client , RIST
- Output parameters section:
 - Host: [Text input field]
 - Port: [Text input field]
 - Password[10-80]: [Text input field]
 - Latency[ms]: [Text input field with value 1000]
 - Encryption type: [Dropdown menu with value None]
 - Bind to IP: [Dropdown menu with value Any]
- Billing Codes:
- Enable decryption:
- Buttons: Ok, Cancel

2. Type in the unique identifier for this output in the **Output Name**.
3. Select an **Input Stream** to be made available on this output from the drop-down list.
4. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
5. Select **SRT Client**.
6. Enter the **Output Parameters** (see Output Stream Parameters Table).
7. If you want to specify **Billing Codes** to identify and differentiate traffic for billing purposes, select this checkbox (see Output Stream Parameters Table below)
8. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see Decrypting an Output Stream in ZEC.
9. Click **OK**.

The new SRT Client Output with its settings is created and now appears on the screen.

ZEC Inputs

ZEC Actions on Input Streams

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Host	The destination host for the SRT stream.
Port	Specify the ports to which the stream will be pushed.
Password	If the stream is password protected, enter the password.
Latency	Specify the maximum latency of the stream in milliseconds. Default: 1000
Encryption Type	Specify the maximum expected bitrate for memory allocation. Recommended: 2X the actual bitrate, which will prevent buffer overruns (especially with VBR streams). Default: 8000. Note – Overflows will typically occur when the Max Bitrate isn't sufficient.
Bind to IP	Select from the drop-down list the local IP address to be used for this output, OR select <i>Any</i> to enable any IP to be used.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable Decryption	Select this checkbox to decrypt an encrypted stream.
Decryption type	If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used. Select Automatic to decrypt a stream that has been encrypted using Automatic encryption. Only if the stream has not been encrypted, select None (default). Important Notice: if the stream has been encrypted you must decrypt it in the output.
Decryption key	If the decryption type includes a key, enter the key to decrypt the stream during output.

ZEC Inputs

ZEC Actions on Input Streams

- Adding RIST Outputs

Playing Input Streams with Players

You can preview the input streams through the following video players:


- Flash Player
- Shoutcast

VLC is only supported in Zixi Broadcaster. A ZEC device can be upgraded to a Zixi Broadcaster by activating a Broadcaster license.

In order to preview an input stream you must first configure its output. See [ZEC Outputs](#) section for more details.


➔ To Play Input Streams with a Flash Player:

Flash Player enables playing the stream on a native browser with the Flash player.

1. In the ZEC **Inputs** page, click the desired input stream that you want to play with Flash Player.
2. Click the  button on the right end of the selected row and then **Play with Flash**. The **Link Description** window with the directory path and proxy path for the desired file is displayed.
3. Copy the directory path and run the .flv file that appears on the first line of the window or click **Play from server** to use HTTP pseudo-streaming for Flash player.

➔ To Play Input Streams with Shoutcast:

Shoutcast enables playing an audio file on a native browser.

1. In the ZEC **Inputs** page, click the desired input stream that you want to play with Shoutcast.
2. Click the  button on the right end of the selected row and then **Play with Shoutcast**. The **Link Description** window will open with the directory path for the desired file.


ZEC Inputs


ZEC Actions on Multiple Inputs

Viewing Traceroutes

For streams sent from a ZEC, you can view traceroute data for the stream.

➔ To view traceroute data:

1. On the **Inputs** page of ZEC, click on the row of the input stream for which you want to view traceroutes.
2. Click the  button on the right end of the selected row and then select **Trace**.
3. The traceroute data for this stream is displayed.






```
Trace for Video_Cast
10/7/2019, 10:15:08 AM
tracertoe --back 85.92.89.244
tracertoe to 85.92.89.244 [85.92.89.244], 30 hops max, 60 byte packets
1  ec2-52-15-0-95.us-east-2.compute.amazonaws.com [52.15.0.95]  5.255 ms  ec2-52-15-0-107.us-east-2.compute.amazonaws.com [52.15.0.107]  5.255 ms  ec2-52-15-0-95.us-east-2.compute.amazonaws.com [52.15.0.95]  5.626 ms
2  100.66.26.0 [100.66.26.0]  1.230 ms  100.66.28.144 [100.66.28.144]  6.827 ms  100.66.27.160 [100.66.27.160]  6.703 ms
3  100.66.12.88 [100.66.12.88]  1.987 ms  100.66.12.118 [100.66.12.118]  6.745 ms  100.66.12.242 [100.66.12.242]  4.165 ms
4  100.66.14.40 [100.66.14.40]  22.774 ms  100.66.15.202 [100.66.15.202]  19.265 ms  100.66.14.228 [100.66.14.228]  16.991 ms
5  100.66.6.78 [100.66.6.78]  14.448 ms  100.66.6.79 [100.66.6.79]  14.446 ms  100.66.6.89 [100.66.6.89]  14.428 ms
6  100.66.4.251 [100.66.4.251]  11.796 ms  100.66.4.25 [100.66.4.25]  15.888 ms  100.66.4.8 [100.66.4.8]  12.669 ms
7  100.66.10.98 [100.66.10.98]  3.332 ms  100.66.8.118 [100.66.8.118]  3.893 ms  100.66.4.248 [100.66.4.248]  0.901 ms
8  52.95.1.121 [52.95.1.121]  1.182 ms  52.95.0.135 [52.95.0.135]  0.519 ms  52.95.0.139 [52.95.0.139]  0.631 ms
9  52.95.2.154 [52.95.2.154]  1.141 ms  52.95.2.228 [52.95.2.228]  1.412 ms  52.95.1.111 [52.95.1.111]  1.141 ms
10  52.95.4.38 [52.95.4.38]  0.753 ms  52.95.4.38 [52.95.4.38]  1.211 ms  52.95.1.207 [52.95.1.207]  1.121 ms
11  100.91.89.94 [100.91.89.94]  1.517 ms  100.91.41.94 [100.91.41.94]  1.818 ms  100.91.41.82 [100.91.41.82]  1.818 ms
12  52.95.86.149 [52.95.86.149]  1.711 ms  52.95.86.149 [52.95.86.149]  1.711 ms  52.95.86.149 [52.95.86.149]  1.711 ms
13  100.91.31.17 [100.91.31.17]  1.517 ms  100.91.31.21 [100.91.31.21]  1.517 ms  100.91.31.69 [100.91.31.69]  1.517 ms
14  52.95.62.23 [52.95.62.23]  1.711 ms  52.95.62.146 [52.95.62.146]  1.711 ms  52.95.62.146 [52.95.62.146]  1.711 ms
15  52.95.62.23 [52.95.62.23]  1.711 ms  52.95.62.138 [52.95.62.138]  1.711 ms  52.95.62.101 [52.95.62.101]  1.711 ms
16  oia-b2-link.teliana.net [62.115.112.150]  2.478 ms  21.478 ms  21.478 ms
17  * nyl-bb4-link.teliana.net [62.115.112.245]  2.261 ms  101.823 ms
18  prs-bb4-link.teliana.net [62.115.114.229]  2.261 ms  101.823 ms
19  prs-bb4-link.teliana.net [62.115.114.229]  2.261 ms  101.823 ms
20  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
21  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
22  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
23  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
24  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
25  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
26  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
27  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
28  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
29  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
30  ffm-bb4-link.teliana.net [62.115.137.129]  2.261 ms  101.823 ms
```

4. You can refresh the Traceroute data at any time by clicking the **Refresh** button.

ZEC Actions on Multiple Inputs

In the Inputs screen, you can perform actions on multiple or all input streams at once by selecting them using the check boxes and then clicking the Marked drop-down menu.



Up Time	TR	101	290	Outputs	Actions
126:40:32	Off			<input type="checkbox"/>	<input checked="" type="checkbox"/>
126:36:12	 P1:  P2:			<input type="checkbox"/>	<input checked="" type="checkbox"/>
00:00:00	Off			<input type="checkbox"/>	<input checked="" type="checkbox"/>

The actions include the following:

Starting and Stopping Multiple Input Streams

You can Start/Stop multiple streams.

➔ To Start/Stop multiple Input Streams:

1. In the ZEC Inputs screen, select the relevant Inputs by selecting the checkboxes

ZEC Inputs


ZEC Actions on Multiple Inputs

2. Click the Marked drop-down menu and then click **Stop** or **Start**.
The selected input streams will be started/stopped.

Deleting Multiple Input Streams

➔ To Delete Multiple Input Streams:

1. In the ZEC Inputs screen, select the relevant Inputs by selecting the checkboxes.
2. Click the **Marked** drop-down menu and then click **Delete**.
The following notification appears:



3. Click **OK**.

Saving Multiple Input Streams

➔ To Save Multiple Input Streams:

1. In the ZEC Inputs screen, select the relevant Inputs by selecting the checkboxes.
2. Click the **Marked** drop-down menu and then click **Save**.
3. All changes to the input streams are saved.

Resetting Stats for Multiple Input Streams

➔ To Reset Stats for Multiple Input Streams:

1. In the ZEC Inputs screen, select the relevant Inputs by selecting the checkboxes.
2. Click the Marked drop-down menu and then click Reset Stats.
All accumulated stream statistics are reset.

Creating a Failover Group

ZEC supports failover based unrecovered packet errors. The trigger for the failover includes unrecovered packets. Through ZEN Master and through the ZEC API it is possible to combine multiple triggers into a Boolean expression to determine when to the trigger the failover. In addition, ZEC features hitless failover for inputs, enabling uninterrupted streaming when switching from one source to another. The hitless failover configuration involves grouping two or more inputs in a "Failover Group". If the inputs are identical (i.e. two or more binary-identical streams with synchronized RTP headers), whenever one of them is disrupted or interrupted completely, ZEC will seamlessly use the packets of the other input without any disruptions by "merging" the streams. The merging of the streams can be achieved using one of the following methods:

- **RTP headers (SMPTE 2022-7)** – if the sources are RTP and the RTP headers were maintained, ZEC will use the SMPTE 2022-7 to compare and merge the two streams in order to allow hitless failover. This option is the most recommended as it will use the sequence and the timestamp in the packets to compare which packets are missing. This method is more accurate than methods that compare the entire payload or methods that use sophisticated DNA sequencing algorithm, which are more error prone, as the payload may have multiple matches.
- **RTP headers or TS content** – if the sources do not have RTP headers, ZEC will try to merge using the MPEG-TS content itself.



If the streams are not identical, the failover process will not be seamless and may take up to a second.

The following procedure describes how to configure inputs as a Failover Group in ZEC.

➔ To create a Failover Group:

1. On the Input screen of ZEC, select the checkboxes of the relevant identical input streams.
2. At the top of the inputs list, click the **Marked** drop-down menu and then click **Failover Group**.

Status	ID	Type	Source	Bitrate[kbps]	Up Time	TR 101 290	Error	Inputs	Actions
Connected	auto-created-push	Push	172.31.35.41	1633	08:17:49	P1: P2:	None	1	<input checked="" type="checkbox"/>
Connected	dup	Push	172.31.35.41	5471	08:17:48	Off	None	1	<input checked="" type="checkbox"/>
Connected	file	File	Chubchub.ts	985	15:38:59	Off	None	1	<input type="checkbox"/>
Offline	his-nonZixi	HLS		0	00:00:00	Off	Stopped	0	<input type="checkbox"/>

- The **Create a Failover Group** window opens:

Create failover group

Stream ID:

Max Outputs:

Show in Matrix:

Stream parameters

Search window[ms]:

Max bitrate [kbps]:

Merge mode:

Candidates

Stream	Min Bitrate[kbps]	Backup
alon_ZEC_source	0	<input type="checkbox"/>
hls_881	0	<input type="checkbox"/>
multi1	0	<input type="checkbox"/>

Billing Codes

Enable multicast on pull outputs

Recording parameters

- In the **Stream ID** field, type a new name for Failover Group. This name will appear in the list of Inputs.
- In the **Max Outputs** field, type the number of desired concurrent outputs that can use the **Failover Group**. Default: Unlimited.
- In the **Search Window** field, type the timeframe in which the system can search for the relevant packets in a matching stream. If there is a latency difference between the streams in the group, the **Search Window** value should be higher than the latency difference between the streams. In case the **Merge Mode** is set to **No Merge**, the **Search Window** time specifies how long the stream will wait for packets before attempting to switch between streams.
- In the **Max Bitrate** field, specify the maximum bitrate of the stream. Default: 8000. This is used for internal memory allocation and will not affect the transmitted bitrate. Recommended: double the bitrate of the highest bitrate stream.
- In the **Merge mode** field, select one of the following:
 - No merge** – select this option if you want ZEC to treat the streams as different and not try to merge the streams. In this case, the time period specified in the


ZEC Inputs

ZEC Actions on Multiple Inputs

Search Window field defines how long the stream will wait for packets before attempting to switch between streams.

- **RTP headers (SMPTE 2022-7)** – select this option if the sources are RTP and the RTP headers were maintained. In this case, ZEC will use the SMPTE 2022-7 to compare and merge the two streams in order to allow hitless failover. This option is the most recommended as it will use the sequence and the timestamp in the packets to compare which packets are missing. This method is more accurate than methods that compare the entire payload or methods that use sophisticated DNA sequencing algorithm, which are more error prone, as the payload may have multiple matches.
 - **RTP headers or TS content** – select this option if you are not sure if the sources do have RTP headers. In this case, ZEC will try to merge using RTP and if not, using the MPEG-TS content itself.
9. Under Candidates, if you want to configure one or more of the streams as back up, select the checkbox next to the relevant stream. Backup streams will be used only when all the "Primary" streams are down.
 10. Configure additional parameters as required.
 11. Click OK.

The Failover Group is added to the list of inputs, listing the sub-streams that are part of the group. The system will automatically detect the offset between the sub-streams and display it in milliseconds under Offset (ms).



Status	ID	Type	Source	Bitrate[kbps]	Up Time	TR 101 290	Error	Outputs	Actions
Connected	fo	Failover		27051	00:00:05	Off	None	0	
Failover components									
Status	Stream	Offset [ms]	Packets						
Connected	test0	0	3046						
Connected	test1	101	0						
Connected	test10	1902	27						

Encrypting an Input Stream in ZEC

You can encrypt a specific input stream using static key AES scrambling encryption (AES 128, AES 192, AES 256). If the stream has been encrypted at the source, it can be encrypted by ZEC only after its decryption (See: [Decrypting an Input Stream in ZEC](#)). The stream encryption prevents any further processing, such as analysis, transcoding, etc.

➔ To encrypt an input stream in ZEC:

1. In **Inputs** screen, click **+New Input**.
2. Select the relevant input type.
3. Fill in the stream parameters.
4. At the bottom, select the **Enable Encryption** checkbox.
5. In the **Encryption Type** field, select **AES 128**, **AES 192**, **AES 256** for fixed encryption.
6. In the **Encryption Key** field, enter your own key or click **Generate** to generate a key by the system. The exact key should be used to decrypt the stream on the other end.

The screenshot shows the 'Add new input stream' dialog box in the ZEC interface. The dialog has a title bar with a search icon and a close button. Below the title bar, there are several input fields: 'Stream ID' (empty), 'Max Outputs' (set to 'Unlimited'), and 'Show in Matrix' (checked). Below these are radio buttons for input types: 'Pull' (selected), 'UDP', 'File', 'RTMP', 'RTSP', 'HLS', 'TS over HTTP', 'SRT', 'SRT Client', 'RIST', and 'NDI'. The 'Stream parameters' section includes fields for 'Host', 'Port' (2088), 'Stream', 'Password', 'Latency [ms]' (4000), 'Ignore TLS certificate errors' (unchecked), and 'Bind to IP' (Any). Below this are checkboxes for 'Billing Codes', 'Transmit as multicast', and 'Decrypt stream'. The 'Enable encryption' checkbox is checked, and the 'Encryption type' is set to 'AES 128'. The 'Encryption key' field is empty, and a 'Generate' button is visible. At the bottom, there are 'Ok' and 'Cancel' buttons. The background shows the 'INPUTS' tab in the ZEC interface.

7. Click **OK**.

Decrypting an Input Stream in ZEC

Any stream that has been encrypted using standard AES static key can be decrypted in ZEC. You can configure the decryption of a specific stream by entering the decryption key.

➔ To decrypt an input stream in ZEC:

1. In **Inputs** screen, click **+New Input**.
2. Select **Pull**.
3. Fill in the input details.
4. At the bottom, select the **Decrypt Stream** checkbox.
5. In the **Decryption Type** field, select **AES 128**, **AES 192**, **AES 256** for fixed key.
6. In the **Decryption Key** field, enter the exact same key that was used to encrypt the stream.


The screenshot shows the 'Add new input stream' dialog box in the ZEC interface. The dialog has a title bar with a close button. Below the title bar, there are several input fields: 'Stream ID' (empty), 'Max Outputs' (set to 'Unlimited'), and 'Show in Matrix' (checked). Below these fields, there are radio buttons for selecting the input type: 'Pull' (selected), 'UDP', 'File', 'RTMP', 'RTSP', 'HLS', 'TS over HTTP', 'SRT', 'SRT Client', 'RIST', and 'NDI'. The 'Stream parameters' section includes fields for 'Host', 'Port' (set to '2088'), 'Stream', 'Password', 'Latency [ms]' (set to '4000'), 'Ignore TLS certificate errors' (unchecked), and 'Bind to IP' (set to 'Any'). Below this, there are checkboxes for 'Billing Codes', 'Transmit as multicast', and 'Decrypt stream' (checked). The 'Decrypt stream' section includes a note: '*Automatic encryption does not require manual settings.' and a dropdown menu for 'Decryption type' (set to 'AES 128') and a text input field for 'Decryption key'. At the bottom, there are checkboxes for 'Enable encryption' and 'Recording parameters'. The dialog ends with 'Ok' and 'Cancel' buttons.


7. Click **OK**.

Demuxing an MPTS Stream

MPTS (Multi Program Transport Streams) streams can be demuxed into single SPTS (Single Program Transport Streams) streams. MPTS demuxing is available for Pull, Push, UDP, and File input streams. From the various programs in the MPTS stream, you can select specific programs, which will be turned into individual SPTS input streams.

➔ **To demux an MPTS stream:**

1. Create a Pull/Push/UDP/File input stream using an MPTS stream.
2. In the **Inputs** page, click the newly created input stream that you want to demux.
3. Click the action  button on the right end of the selected row and then **Edit**. The Edit input stream name window is displayed.
4. Select the **Demux MPTS** checkbox.
A list of included programs is displayed.



5. Click **Add Program** on the program that you want to create a separate SPTS input stream.
An **Add Input** screen opens with the new SPTS input details, including a suggested

ZEC Inputs

Demuxing an MPTS Stream

Stream ID, the original MPTS as a Source Stream and the relevant **Program** number.

Program #4 of stream MPTS_example

Stream ID: MPTS_example_program

Max Outputs: Unlimited

Show in Matrix:

Stream parameters

Source stream: MPTS_example

Program: 4

Max bitrate [kbps]:

Enable time shift

Transmit as multicast

Enable encryption

Recording parameters

Ok Cancel

6. In the **Max Bitrate** field, specify the maximum bitrate of the stream. This is used for internal memory allocation and will not affect the transmitted bitrate. Recommended: double the bitrate of the highest bitrate stream.
7. Configure additional parameters as necessary.
8. Click **OK**.

The channel is assigned an input:

Push Pull UDP Delayed File RTMP RTSP HLS TS over HTTP

Stream parameters

Path: Curtis/MC_HD_Audio_Channels.ts

Enable time shift

Transmit as multicast

Enable encryption

Demux MPTS

Program#	Name	Provider	Assigned input
1			
4			MPTS_example_program_4
5			
6			
7			
-			

+ Add program

+ Add program

+ Add program

+ Add program

9. Repeat steps 5-8 to add more programs.
10. Click **OK**.

The newly created MPTS input stream and the related SPTS input streams will appear in

ZEC Inputs

Viewing TR101 Analysis


the Inputs list.

Status	ID	Type	Source	Bitrate[kbps]	Up Time	TR 101 290	Error	Outputs	Actions
Connecting	mpts2	Pull	demo.zixi.com:2088	0	00:00:00	Off	No Source	0	
Connected	MPTS_example	File	Curtis/MC_HD_Audio_Channels.ts	19025	04:01:31	Off	None	0	
Connected	MPTS_example_program...	SPTS	MPTS_example.Program#4	497	00:07:15	Off	None	0	
Connected	Music_Choice_MPTS	File	Curtis/MC_HD_Audio_Channels.ts	19010	136:38:52	P1: P2:	None	1	

Viewing TR101 Analysis

TR101 analysis can be added to an input stream for the monitoring of the TS while in operation. The analysis can be used to check the integrity of the TS, as well as perform content analysis to identify frozen video, blank picture, silent audio, low video quality and audio clipping. The TR101 analysis covers priority 1 and 2 messages.

To enable the TR101 analysis follow the instructions in the [Adding TR101 Analysis to the Input Stream](#) section. After enabling the analysis, the stream will include the P1 (high priority error) and P2 (low priority error) status, indicating is there are P1 or P2 messages.

To open the analysis window, click the stethoscope () icon.

The TR101 Analysis window includes the following elements:

Stream analysis: hls_881

Stream Information Statistics

- Status
 - TR101 performance drops: 0
 - CQA performance drops: 0
 - Error: None
- PAT
 - Min bitrate: 14kbps (1.4%)
 - Max bitrate: 14kbps (1.4%)
 - Avg bitrate: 14kbps (1.4%)
 - CC errors: 204
 - Scrambled: 0
 - Packets: 1339356
- NULL
 - Min bitrate: 0kbps (0%)
 - Max bitrate: 0kbps (0%)
 - Avg bitrate: 0kbps (0%)
 - Packets: 5291059
- Programs
 - Program #1 - Service01
 - Provider: FFmpeg
 - PMT PID: 4096 (0x1000)
 - Min bitrate: 14kbps (1.4%)
 - Max bitrate: 14kbps (1.4%)
 - Avg bitrate: 14kbps (1.4%)
 - CC errors: 204

Indicator #Errors Last error Error message

Priority 1

- TS_sync_loss 0 -- --
- Sync_byte_error 0 -- --
- PAT_error 0 -- --
- Continuity_count_error 408 2022-Nov-02 09:07:01 Continuity count error on PID 4096. Expected:9 Detected: 14
- PMT_error 0 -- --
- PID_error 0 -- --

Priority 2

- Transport_error 0 -- --
- CRC_error 0 -- --
- PCR_error 0 -- --
- PCR_accuracy_error 1500843 2022-Nov-02 09:40:25 PCR accuracy of selected program is not within 500ns. (2.58433e+07ns) PID:256
- PTS_error 0 -- --
- CAT_error 0 -- --

Content analysis

- Frozen_video 0 -- --
- Blank_picture 0 -- --
- Silent_audio 0 -- --
- Low_video_quality 0 -- --
- Audio_clipping 0 -- --

P1/P2 Errors

Content analysis errors

Analysis Controls

Content Analysis: Enable Refresh Reset Close

Stream Information Statistics Panel

The stream information statistics panel displays the following accumulative statistics about the stream:

Parameter	Description
Status	
TR101 performance drops	The number of packets dropped from the analyzer due to low performance. This indicates how many video frames were not able to be analyzed due to the CPU being overloaded.
CQA performance drops	Measures content quality. Displays the number of content quality performance drops over time. This indicates how many video frames were not able to be analyzed due to the CPU being overloaded.
Error	Displays the number of errors.
PAT	The Program Association Table (PAT), which only appears in PID 0x0000 packets, tells the decoder what programs are in the TS and points to the Program Map Tables (PMT) which in turn point to the component video, audio and data streams that make up the program. If the PAT is missing then the decoder can do nothing, no program is decodable.
Min bitrate	The minimum bitrate of the PAT packets.
Max bitrate	The maximum bitrate of the PAT packets.
Avg bitrate	The average bitrate of the PAT packets.
CC errors	Indicates if continuity count errors were found. For this indicator three checks are combined. The preconditions "Incorrect packet order" and "Lost packet" could cause problems for IRD which are not equipped with additional buffer storage and intelligence. It is not necessary for the test equipment to distinguish between these two preconditions as they are logically OR-ed, together with the third precondition, into one indicator.
Scrambled	Indicates if the packet is encrypted.
Packets	The number of packets which are related to the PAT (with the same PID – 0)
NULL	Null (stuffing) packets. In order to ensure that the stream maintains a constant bitrate, a multiplexer may need to insert some additional packets. The PID 0x1FFF is reserved for this purpose. The payload of null packets is all zeroes, and the egress component is expected to ignore its contents. Null packets are indicated by PID 8191 (all 1s).

ZEC Inputs

Viewing TR101 Analysis

Min bitrate	The minimum bitrate of the NULL packets.
Max bitrate	The maximum bitrate of the NULL packets.
Avg bitrate	The average bitrate of the NULL packets.
Packets	The number of packets which are related to NULL (with the same PID 8191)
Programs	<p>The Transport Stream can include one program (SPTS) or multiple programs (MPTS).</p> <p>Every program is described by a program map table (PMT). The elementary streams associated with that program have PIDs listed in the PMT. Another PID is associated with the PMT itself.</p>
Provider	Extracted from the MPEG-TS SDT table (if exist in stream).
PMT PID	Indicates the PID number of the program map table PMT.
Min bitrate	The minimum bitrate of the packet which is related to the PMT PID.
Max bitrate	The maximum bitrate of the packet which is related to the PMT PID.
Avg bitrate	The average bitrate of the packet which is related to the PMT PID.
CC errors	Indicates if continuity count errors were found in the packets that are related to the PMT PID. For this indicator three checks are combined. The preconditions "Incorrect packet order" and "Lost packet" could cause problems for IRD which are not equipped with additional buffer storage and intelligence. It is not necessary for the test equipment to distinguish between these two preconditions as they are logically OR-ed, together with the third precondition, into one indicator.
Packets	The number of packets which are related to the PMT PID.
PCR PID	Indicated the PID value that includes the program clock reference (PCR). The PCR is used to enable a decoder to present synchronized content, such as audio tracks matching the associated video.
PCR	Indicates the program clock reference (PCR) value.
Accuracy	Indicates the difference between the actual PCR value and the value it should have in the TS represented by the byte index for its actual position. For example, if the calculated PCR (derived from adding the value to the previous packet) is the same as the actual PCR value, the Accuracy value will be '0'.
Deviation	Indicates the frequency deviation.
Delay	Indicates the delay in delivery.
OJ max	Indicates the maximal Overall Jitter, which are variation in delays.

ZEC Inputs

Viewing TR101 Analysis

OJ Dev	Indicates the deviation in the overall jitter.
Bitrate	The bitrate of the specific PCR PID packets.
Elementary PIDs	<i>Below the Elementary PIDs level are all the different programs that are included in the stream.</i>
Type	The type of program.
Aligned PES	Indicates if the stream is PES aligned (i.e. syncword start right after the mpeg-ts PES header).
Min Bitrate	The minimum bitrate of the packet which is related to the Elementary PID.
Max Bitrate	The maximum bitrate of the packet which is related to the Elementary PID.
Avg Bitrate	The average bitrate of the packet which is related to the Elementary PID.
Declared Bitrate	The bitrate value which that was set on the encoder. (H264 streams only).
HDR Buffer Size	The HRD buffer size that was set on the encoder. (H264 streams only)
CC errors	Indicates if continuity count errors were found in the packets that are related to the Elementary PID.
Scrambled	Indicates if the packet is encrypted. Possible values include: Not scrambled, scrambled with even key, scrambled with odd key.
PIC Timing	Indicates the time as it appears in the last PIC Timing SEI message. (H264 streams only).
PTS	The Presentation Time Stamp (PTS) that the analyzer has captured on the Element stream. The PTS is only accessible if the TS is not scrambled.
DTS	The Decode Time Stamp (DTS) that the analyzer has captures on the Element stream. The Decode Time Stamp (DTS) indicates the time at which an access unit should be instantaneously removed from the ZEC (as a receiver) buffer and decoded. It differs from the Presentation Time Stamp (PTS) only when picture reordering is used for B pictures. If DTS is used, PTS must also be provided in the bit stream. PTS (or DTS) is entered in the bitstream at intervals not exceeding 700 mS. ATSC further constrains PTS (or DTS) to be inserted at the beginning of each access unit.
Total Bytes	The total amount of bytes that has passed through the current elementary stream. This includes the Transport Stream Headers.
Packets	The total amount of packets that have passed through the current elementary stream.
Width	The frame resolution width setting.

ZEC Inputs

Viewing TR101 Analysis

Height	The frame resolution height setting.
FPS	The Frames Per Second setting.
Interlaced	Indicates whether the video is interlaced or not.
Chroma	Indicates the Chroma Subsampling.
CEA-608/708 captions	A counter that shows how many SEI messages with type 4 (user_data_registered_itu_t_t35) were detected so far. (H264 and HEVC streams only)
Sample rate	Sampling rate of audio, as reported in the stream.
Reported Channels	The number of audio channels reported in the stream.
Frames	Indicates the number of frames. This indicator is enabled when content analysis is turned on.
Content	Indicates the status of the content. This indicator is enabled when content analysis is turned on. Possible values: <ul style="list-style-type: none">• Live – indicates that there is a difference between two consecutive frames within a period of 30 seconds.• Frozen video – indicates that there is a single frame that is displayed (frozen).• Blank picture – the entire frame is in one color (e.g. black, white, etc.).• Unknown – this status is displayed during the first 30 seconds of the content analysis.
ePSNR	Estimated PSNR - an estimation of the video quality. values in dB
PSNR	Actual PSNR as calculated by the encoder. Available on software transcoded H264 streams only (when user turned it on under the settings tab). values in dB.
Chroma bit depth	Video bit depth.
Luma bit depth	Video bit depth
Channel 1	The audio level of channel #1.
Channel 2	The audio level of channel #2.
Frames	Indicates the number of frames. This indicator is enabled when content analysis is turned on.
Frame Duration max/min/avg (ms)	Indicates the maximum, minimum, and average frame duration in milliseconds.
GOP Duration max/min/avg (ms)	Indicates the maximum, minimum, and average GOP duration in milliseconds.

ZEC Inputs

Viewing TR101 Analysis

GOP structure	Indicates the GOP structure, by showing the first 10 frame types in the last GOP. For the example, IPBBBBBBBB.
----------------------	--

P1/P2 Errors

The P1/P2 errors panel displays data about Priority 1 and Priority 2 errors that were found in the stream during the analysis. The table displays the following information for each error:

- **Indicator** – the indicator for which the error was generated.
- **#Errors** – the total number of errors that were generated.
- **Last error** – the time in which the last error was generated.
- **Error message** – the message that was generated with the error.

The statistics regarding the following Priority 1 and Priority 2 errors are displayed.

Parameter	Description
Priority 1	
TS_sync_loss	Indicates a loss of synchronization with the TS. When 5 sync bytes have been acquired, the decoder is considered synched, but a loss of just 2 sync bytes indicates a loss of sync.
Sync_byte_error	If the sync byte is not equal to 47 hexidecimals, then a sync byte error occurs. The system then looks for the reoccurrence of the sync byte (which must be 47 hexadecimals) every 188 bytes.
PAT_error	The program association table (PAT) is the only packet with packet ID (PID) Hex 0000, and it must occur at least every 0.5s to keep this error from occurring. Every program within the TS is listed in the PAT; if it is missing, then no programs can be decoded
Continuity_count_error	This error occurs when any of the following faults happen — incorrect packet order, a packet occurs more than twice or a packet is lost.
PMT_error	This error can occur if the program map table (PMT) does not come up at least every 0.5s on the PID that is referred to in the PAT.
PID_error	When TSes are remultiplexed, this can occur if any PID doesn't refer to an actual data stream.
Priority 2	
Transport_error	This flag is set in the TS header by the demodulator if it can't correct errors in the stream.

ZEC Inputs

Viewing TR101 Analysis

CRC_error	This indicates that a CRC error (data corruption) occurred in any of the following tables — CAT, PAT, PMT, NIT, EIT, BAT, SDT or TOT.
PCR_error	This flag is raised if the primary clock reference (PCR) is not seen for more than 100ms. The time interval between two consecutive PCR values should be no more than 40ms. This type of error can cause the decoder to lose lock on the 27MHz clock.
PCR_accuracy_error	This error can occur when the PCR accuracy of the selected program is outside the range of ± 500 ns.
PTS_error	This occurs when the presentation time stamp (PTS) repetition is more than 700ms. The PTS is contained in the MPEG-2 program stream and is used to aid the decoder in presenting the program on time, at the correct speed and synchronized. The PTS is compared to the PCR.
CAT_error	This is used for conditional access programs (paid programming).

Content Analysis

The Content Analysis errors panel displays that were found in the stream as part of ZEC's content analysis. To see this table, you must enable the content analysis, by following the instructions in the [Enabling Content Analysis](#) section. The table displays the following information for each error:

- **Indicator** – the indicator for which the error was generated.
- **#Errors** – the total number of errors that were generated.
- **Last error** – the time in which the last error was generated.
- **Error message** – the message that was generated with the error.

Parameter	Description
Frozen_video	Occurrence of frozen video, i.e. no motion, for a duration of approximately 60s or longer.
Blank_picture	Occurrence of blank frames of any color for a duration of approximately 60s or longer.
Silent_audio	Occurrence of silence (dBFS < -90) on AAC or MPEG audio with a duration of about 30s or longer.
Low_video_quality	The estimated video quality, which is based on the Peak signal-to-noise ratio (PSNR) is below the 20dB threshold and therefore considered as poor.
Audio_clipping	Occurrence of clipped audio upon occurrence on AAC or MPEG audio.

Enabling Content Analysis

12. ZEC's content analysis can be enabled and disabled using the Stream Analysis screen.

➔ **To enable content analysis:**

1. Add TR101 Analysis to an input stream. See [Adding TR101 Analysis to the Input Stream](#)
2. Click the stethoscope icon shown in the TR 101 290 column. The Stream Analysis screen is displayed.
3. On the Stream Analysis screen, select **Content Analysis: Enable** from the Content Analysis drop-down menu.

To disable Content Analysis, select **Content Analysis: Disable** from the Content Analysis drop-down menu.

ZEC Outputs

ZEC supports the following output types:

- **UDP** – Target is a UDP or RTP stream, over unicast or multicast.
- **RTMP** – Real Time Messaging Protocol streams can be played on systems that accept this protocol as input. Originally designed to enable Adobe® Flash® streams to be sent between a server and a client, RTMP has become a popular protocol for streaming into content-delivery networks (CDNs).
- **RTMPS** – RTMP over a TLS/SSL connection.
- **Push Stream** – Push streams are Zixi protocol streams destined for other ZEC instances and ZEC in “Accept mode”.
- **TCP** – TCP protocol provides reliable transmission guarantee for no loss of frame. Its bandwidth probing and congestion control will attempt to use all of the available bandwidth between the server and client, fetching content as quickly as possible while being friendly to other (TCP) traffic on the same links. Output streams can be pushed to one ZEC instance.
- **HTTP Push** – The HTTP Push output stream can be encapsulated in HLS or DASH. The source of the output stream is a predefined adaptive group that has been configured in the [Adaptive Groups](#) screen. The configuration of the stream includes the option to delete outdated stream fragments on the server. Output streams can be pushed to one ZEC instance.
- **S3 Bucket** – The HTTP output stream (HLS or DASH) can be pushed to an AWS S3 Bucket. The native S3 support includes the ability to configure the S3 authentication credential, including the Region, Access Key, and Secret Key.
- **SRT Caller/Push** – The SRT output can be pulled to/from an SRT-enabled device and is configured via Zen Master or ZEC API only. SRT stands for ‘Secure Reliable Transport’ and is an open-source video transport protocol and technology stack. SRT uses secure streams and easy firewall traversal to optimize streaming performance and deliver high-quality video over even the most unreliable networks.
- **SRT Listener/Pull** – The SRT Client output can be pushed to an SRT-enabled device and is configured via Zen Master or Zixi API only. SRT stands for ‘Secure Reliable Transport’ and is an open-source video transport protocol and technology stack. SRT uses secure streams and easy firewall traversal to optimize streaming performance and deliver high-quality video over even the most unreliable networks.
- **RIST** – The RIST output can be pushed or have them pulled to/from a RIST-enabled device. RIST seeks to provide reliable, high performance media transport by using UDP at the transport layer to avoid the inefficiencies of TCP, then layering on top Forward Error Correction and Retransmits to add the reliability inherently absent from UDP.

ZEC Outputs

Viewing TR101 Analysis

When ZEC pulls a stream, a Pull stream definition is generated automatically in ZEC, the stream is identified in the Name and Destination columns of ZEC with the ID and IP address of the ZEC instance that pulls the stream.

ZEC Outputs

Instead of manually creating an output and then connecting the output to an input, you can define output templates with rules for automatic creation of outputs with predefined settings. The template includes an Input pattern. When an input pattern matches

Automated Output Configuration with Output Templates

Instead of manually creating an output and then connecting the output to an input, you can define output templates with rules for automatic creation of outputs with predefined settings. The template includes an Input pattern. When an input pattern matches the pattern of an incoming input stream, the output is created automatically. For more information about Output Templates, see Decrypting an Output Stream in ZEC

Any stream that has been encrypted using standard AES static key can be decrypted in ZEC. You can configure the decryption of a specific stream by entering the decryption key.

➔ To decrypt an output stream in ZEC:

1. In **Outputs** screen, click **+New Output**.
2. Select **UDP, RTMP, TCP, SRT, SRT Client** or **RIST**.
3. Fill in the output details.
4. At the bottom, select the **Enable decryption** checkbox.
5. In the **Decryption type** field, select **AES 128, AES 192, AES 256** for fixed key.
6. In the **Decryption Key** field, enter the exact same key that was used to encrypt the stream.

ZEC Outputs

Instead of manually creating an output and then connecting the output to an input, you can define output templates with rules for automatic creation of outputs with predefined settings. The template includes an Input pattern. When an input pattern matches

The screenshot shows a 'New output' dialog box with the following fields and options:

- Output Name:** Text input field.
- Input Stream:** Dropdown menu.
- Show in Matrix:**
- Protocol Selection:** UDP (selected), RTMP, Push, TCP, HTTP Push, AWS, SRT, SRT Client, RIST.
- Output parameters:**
 - Host:** Text input field.
 - Port:** Text input field, **TTL:** Text input field.
 - Smoothing [ms]:** Text input field with value 0.
 - RTP:**
 - Bind to IP:** Dropdown menu with value Any.
 - Local port:** Text input field.
- Billing Codes:**
- Remultiplex/Pad:**
- Enable decryption:**
 - Decryption type:** Dropdown menu with value AES 128.
 - Decryption key:** Text area.
- Enable IFB/Talkback:**

Buttons: **Ok**, **Cancel**

7. Click **OK**.

Using Output Templates.

Adding Outputs

ZEC enables you to add various types of outputs. When you create a new output, select the output type and then fill in the fields that are applicable for that output type.

Adding UDP Outputs

This enables ZEC to send a UDP stream. The UDP stream is not protected by the Zixi protocol. The UDP streams can be one of the following types:

- UDP – plain UDP
- RTP – Real-Time Transport Protocol
- RTP + SMPTE 2022 FEC - SMPTE 2022 standard with Forward Error Correction

➔ To Create a UDP Output:

1. In the ZEC **Outputs** page, click **+ New Output**. The **New output** window is displayed.

The screenshot shows the 'New output' dialog box in the ZEC interface. The dialog is titled 'New output' and has a close button (X) in the top right corner. It features a tabbed interface with 'OUTPUTS' selected. The 'Output Name' field is empty. The 'Input Stream' is selected from a dropdown menu. The 'Show in Matrix' checkbox is checked. Below this, there are radio buttons for output types: 'UDP' (selected), 'RTMP', 'Push', 'TCP', 'HTTP Push', 'AWS', 'SRT', 'SRT Client', and 'RIST'. Under 'Output parameters', there are fields for 'Host', 'Port', 'Smoothing [ms]' (set to 0), 'RTP' (checkbox), 'Bind to IP' (set to 'Any'), and 'Local port'. At the bottom, there are four checkboxes: 'Billing Codes', 'Remultiplex/Pad', 'Enable decryption', and 'Enable IFB/Talkback', all of which are unchecked. 'Ok' and 'Cancel' buttons are at the bottom right. A timestamp '3wy0@172.31.35.41' is visible at the bottom of the dialog.


2. Type in the unique identifier for this output in the **Output Name**.
3. Select an **Input Stream** to be made available on this output from the drop-down list.
4. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.

ZEC Outputs

Adding Outputs

5. Select **UDP**.
6. Specify the **Output parameters** (see Output Stream Parameters Table).
7. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameter Table below).
8. If you want to remux the stream to CBR (used for professional IRDs) in order to avoid bandwidth waste or add NULL packets and adjust the stream clock (PCR) in order to make the stream CBR, select Remultiplex/Pad and configure the respective parameters (see Output Stream Parameters Table).
9. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see [Decrypting an Output Stream in ZEC](#).
10. If you want to enable the ZEC decoder to send audio back to the ZEC encoder, select the IFB/Talkback checkbox.
11. Click **OK**.
12. The new UDP Output with its settings is created and now appears on the **Outputs** screen.

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Host	Specify the destination IP address or URL.
Port	Specify the target UDP port.
TTL	Specify the time-to-live (TTL). Used mainly to limit the range (or “scope”) of a multicast transmission. Leaving it as blank uses the default value specified by the operating system.
Smoothing [mms]	Enables transmission of the output at the correct rate. Required when the receiving device is sensitive and can’t lock on to the stream (in such a case, the recommended latency is 100 - 1000 ms).
RTP	Enables use of the Real-time Transport Protocol.
SMPTE 2022 FEC:	Disables the FEC or specify the type of FEC matrix to D1/ D2.  This setting can be modified without interrupting an existing stream. In the SMPTE-2022 FEC standard, 1-D and 2-D parity codes are systematic FEC codes of decent complexity that provide protection against bursty or random losses. To

ZEC Outputs

Adding Outputs

	<p>enable SMPTE-2022 FEC (Forward Error Correction) select one of the following parity options from the drop-down menu:</p> <ul style="list-style-type: none">• 1D (single dimension FEC) - SMPTE-2022 1D can fix a problem in ONE packet per row. This means that the number of rows specified should consider the packet loss rate- the shorter the row, the more error resilience can be achieved on the expense of bitrate level. However, longer rows increase the delay that the FEC will add. It is recommended to select this option when the packet loss is sporadic. The stream will occupy the source port and two ports above it (e.g. if the source port is 8988, it will occupy 8990).• 2D - SMPTE-2022 2D uses a table of packets, which includes rows and columns. This option is more error resilient, but it increases the delay by (row*column) packets and increases the bitrate with R+C packets per each table of R*C packets. It is recommended to select this option when packet loss is bursty. The stream it will occupy four ports above (e.g. if the source port is 8988, it will occupy 8992).
Bind to IP	Select from the drop-down list the local IP address to be used for this Output, OR select <i>Any</i> to enable any IP to be used.
Local Port	Specify from which local port to source the stream, if desired (instead of randomly chosen by the operating system).
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Remultiplex/Pad	Select this checkbox to enable remuxing from VBR MPEG-TS to MPEG-TS CBR (used for professional IRDs) or padding with null packets.
Mode	<p>Select one of the following:</p> <ul style="list-style-type: none">• Pad – adds NULL packets and adjusts the stream clock (PCR) in order to make the stream CBR.• Remultiplex - performs demux->mux and rebuilds the stream according to the below parameters.
Target bitrate [kbps]:	Specify the CBR bitrate to target for a remuxed stream.

ZEC Outputs

Adding Outputs

Buffer Size [ms]	Specify the size of the buffer that will be used for the remixing. A larger buffer increases the quality, but also increases latency.
No NULL Packets	Select this option to re-multiplex the stream to CBR but remove the NULL packets in order to maintain low bitrate.
Enable Decryption	Select this checkbox to decrypt an encrypted stream.
Decryption type	<p>If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used.</p> <p>Select Automatic to decrypt a stream that has been encrypted using Automatic encryption.</p> <p>Only if the stream has not been encrypted, select None (default).</p> <p>Important Notice: if the stream has been encrypted you must decrypt it in the output.</p>
Decryption key	If the decryption type includes a key, enter the key to decrypt the stream during output.
Enable IFB/Talkback	Select this checkbox to enable IFB/Talkback for one-way communication from the director or assistant director to on-air talent or a remote location. Selecting the checkbox allows the ZEC decoder to send audio back to the ZEC encoder. This offers the ability to, for example, give audio feedback to the camera operator.
Port	The port that will be used to send the audio feedback.

Adding RTMP and RTMPS Outputs

Real Time Messaging Protocol streams can be played on systems that accept this protocol as input. Originally designed to enable Adobe® Flash® streams to be sent between a server and a client, RTMP has become a popular protocol for streaming into content-delivery networks (CDNs).



To create an RTMPS output, select the RTMP output option but make sure `rtmps://` url is used in the URL field.



SCTE-35 markers in MPEG-TS streams trigger OnCuePoint call function in RTMP.

➔ To create an RTMP Output:

1. In the ZEC **Outputs** page, click [+ New Output](#). The **New output** window is displayed.

ZEC Outputs

Adding Outputs

2. Type the unique identifier for this output in the **Output Name**.
3. Select an **Input Stream** to be made available on this output from the drop-down list.
4. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
5. Select **RTMP**.
6. Specify the **Output parameters** (see Output Stream Parameters Table).
7. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameter Table below).
8. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see [Decrypting an Output Stream in ZEC](#).
9. Click **OK**.
The new RTMP Output with its settings is created and now appears on the screen.

Output Stream Parameters Table

Parameter	Description
-----------	-------------

ZEC Outputs

Adding Outputs

Output Parameters	
URL	<p>Specify the destination Stream URL according to the following format: <code>rtmp://host:[port]/app</code>.</p> <p>You can define RTMPS clients with the proven security of a secure socket layer (SSL), by using the <code>rtmps://</code> url. Note that Facebook currently supports RTMPS streams only.</p>
Backup URL	<p>Enter a backup URL (fallback mode) – will be used in case the primary server is not responsive.</p>
Stream Name	<p>Specify the unique name for the stream that the RTMP server at the other end of the connection expects.</p>
Username	<p>Specify the Username to authenticate on the remote RTMP server</p>
Password	<p>Specify the string that is used for authorization on the remote RTMP server.</p>
Bitrate (kbps)	<p>Specify the actual bitrate in kbps or the maximum stream bitrate in case of a VBR stream.</p>
Reconnect (sec)	<p>If the stream drops, this value represents the time between reconnection attempts (in seconds). Default: 5.</p>
Bind to IP	<p>Select from the drop-down list the local IP address to be used for this Output, OR select <i>Any</i> to enable any IP to be used.</p>
Send Timecode	<p>Converts the MPEG-TS SEI section to RTMP ONFI command (pass the encoder timecodes to the RTMP server)</p>
Disconnect if inactive	<p>Select this checkbox to disconnect if the stream is not active for 30 seconds.</p>
Ignore TLS certificate errors	<p>Select this option when streaming to a trusted server that does not have a valid certificate. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.</p>
Billing Codes	<p>Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.</p>
Billing Code	<p>Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.</p>
Billing password	<p>Enter the password that corresponds to this billing code.</p>

ZEC Outputs

Adding Outputs

Enable Decryption	Select this checkbox to enable decryption of an encrypted stream.
Decryption type	<p>If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used.</p> <p>Select Automatic to decrypt a stream that has been encrypted using Automatic encryption.</p> <p>Only if the stream has not been encrypted, select None (default).</p> <p>Important Notice: if the stream has been encrypted you must decrypt it in the output.</p>

ZEC Outputs

Adding Outputs

Adding Push Outputs

Output streams can be pushed to one or ZEC instances. You can specify multiple destinations by adding them in the Links section. You can also split a single stream using multiple links and then bond them into a single stream in the target ZEC instance using the Bond Links feature. For each of these links, you can specify the max bitrate that can be used. In addition, some links may be specified as backups. The backup links will be used if the bandwidth across all the non-backup links are not enough for the stream (i.e. if a non-backup link is not available, it will not use the backup). Only if the accumulated bandwidth of non-backup links is not enough, then ZEC will stream to a backup link.

The error recovery techniques implemented in the Zixi protocol Push streams are protected under U.S. patent 11,546,615.

➔ To Create a Push Output:

1. In the ZEC **Outputs** page, click [+ New Output](#).
The **New Output** window is displayed.

The screenshot shows the 'New output' dialog box in the ZEC interface. The dialog is titled 'New output' and has a close button (X) in the top right corner. It features a navigation bar at the top with tabs: OUTPUTS (selected), ADAPTIVE, VOD, SETTINGS, EVENT LOG, and MATRIX. Below the navigation bar, there are input fields for 'Output Name:', 'Input Stream:', and 'Show in Matrix:' (with a checked checkbox). A radio button group allows selecting the output type: UDP, RTMP, Push (selected), TCP, HTTP Push, AWS, SRT, SRT Client, and RIST. The 'Output parameters' section includes a 'Links' table with columns for Host, Port (set to 2088), and IP (set to Any), along with a 'Bond Links' checkbox. Below this are fields for 'Stream ID:', 'Password:', 'Max latency [ms]:' (set to 4000), and 'Ignore TLS certificate errors:' (checkbox). At the bottom, there are three checkboxes: 'Billing Codes', 'Enable encryption', and 'Enable IFB/Talkback'. 'Ok' and 'Cancel' buttons are located at the bottom right of the dialog.

2. Type in the unique identifier for this output in the **Output Name**.
3. Select an **Input Stream** to be made available on this output from the adjacent drop-down list.

ZEC Outputs

Adding Outputs

4. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
5. Select **Push**.
6. Do one of the following:
 - a. **Stream to multiple destinations** - you can stream the same identical stream to multiple destinations by entering the destination parameters and then clicking the "+" button to add another destination (see **Output Stream Parameters Table**).
 - b. **Bonded link to a single destination** - you can split the stream into multiple links, which will be forwarded to a single ZEC instance by selecting the **Bond Links** checkbox (see **Using Network Bonding for Hitless Failover**).
7. Enter additional parameters as necessary (see Output Stream Parameters Table).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameter Table below).
9. If you want to encrypt the Output stream, select the **Enable encryption** checkbox.
10. If you want to enable the ZEC decoder to send audio back to the ZEC encoder, select the **IFB/Talkback** checkbox.
11. Click **OK**.

The new Push Output with its settings is created and now appears on the screen.

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Links	
Host	The destination host for the push stream. Note: additional failover destinations can be added by clicking the adjacent "+" button.
Port	Specify the ports to listen on for Push streams. Default: 2088.
IP	Specify the local IP address.
Bond Links	Click this checkbox to split the stream into multiple links, which will be forwarded to a single ZEC instance.
Max Bitrate (for Bond Links enabled)	Relevant for Bond Links option. Specify the max bitrate in Kbps for the specific link.

ZEC Outputs

Adding Outputs

Backup (for Bond Links enabled)	Relevant for Bond Links option. Select this checkbox to define the link as a backup. The backup will be used only if the accumulated bandwidth of the non-backup links is not sufficient.
Stream ID	Specify the unique Stream ID that the remote ZEC expects.
Password	Optional - Specify a string to be used at the receiving ZEC to authenticate that the pushing ZEC is allowed to push this stream.
Max Latency [ms]	Specify the buffer size that ZEC will keep for error correction. For example, 6000 milliseconds would ensure that the stream is protected for six seconds of errors in the network. Default:6000
Ignore TLS certificate errors	Select this option when streaming to a trusted server that does not have a valid certificate. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable Encryption	Select this checkbox to encrypt the Output stream.
Encryption type (for Encryption enabled)	Specify the type of Encryption (AES 128/192/256). Click Generate to generate an encryption key or enter another encryption key.
Enable IFB/Talkback	Select this checkbox to enable IFB/Talkback for one-way communication from the director or assistant director to on-air talent or a remote location. Selecting the checkbox allows the ZEC decoder to send audio back to the ZEC encoder. This offers the ability to, for example, give audio feedback to the camera operator.
Port	The port that will be used to send the audio feedback.

Adding TCP Outputs

TCP protocol provides reliable transmission guarantee for no loss of frame. Its bandwidth probing and congestion control will attempt to use all of the available bandwidth between the server and client, fetching content as quickly as possible while being friendly to other (TCP) traffic on the same links. The TCP output can push the stream directly to a TCP socket or to an HTTP server.

MultiPath TCP

Developed by the Internet Engineering Task Force's (IETF) Multipath TCP working group, MultiPath TCP (MPTCP) is an effort towards enabling the simultaneous use of several IP-addresses/interfaces by a modification of TCP that presents a regular TCP interface to applications, while in fact spreading data across several subflows. ZEC supports MultiPath TCP for Linux based on the OS Kernel support. This means that the Linux Kernel should be updated to support MPTCP. For detailed information on how to update the Kernel and use MPTCP, see [Configuring MultiPath TCP](#).

The MPTCP functionality is similar to ZEC's "multi-link bonding" feature, which is available for UDP only. In this case MPTCP works on TCP.

If both the sending end and the receiving end support MultiPath TCP, ZEC can use this functionality to transmit a stream over TCP using multiple network interfaces (e.g. Wifi + mobile). The multiple links can be configured to:

- **Aggregate** - aggregate the bandwidth of the multiple links in order to use the total capacity of the links. In this case ZEC will use all available bandwidth among all available flows (if needed) to send the stream.
- **Duplicate** - enhance the path's resiliency by duplicating the stream and sending through multiple links in order to overcome errors and packet loss.

➔ To Create a TCP Output:

1. In the ZEC **Outputs** page, click . The **New Output** window is displayed.

ZEC Outputs

Adding Outputs

The screenshot shows a 'New output' dialog box with the following fields and options:

- Output Name: [Text input field]
- Input Stream: [Dropdown menu]
- Show in Matrix:
- Protocol selection: UDP, RTMP, Push, TCP, HTTP Push, AWS, SRT, SRT Client, RIST
- Output parameters section:
 - Host: [Text input field]
 - Port: [Text input field]
 - HTTP:
- Billing Codes:
- Enable decryption:
- Buttons: Ok, Cancel

2. Type in the unique identifier for this output in the **Output Name**.
3. Select an **Input Stream** to be made available on this output from the adjacent drop-down list.
4. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
5. Select **TCP**.
6. Specify the Output parameters (see **Output Stream Parameters** Table).
7. If the target is an HTTP server, select the **HTTP** checkbox. In this case, HTTP headers will be added to the stream.
8. Enter additional parameters as necessary (see Output Stream Parameters Table).
9. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameter Table below).
10. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see [Decrypting an Output Stream in ZEC](#).
11. Click **OK**. The new TCP Output with its settings is created and now appears on the screen.

Output Stream Parameters Table

Parameter	Description
Output Parameters	

ZEC Outputs

Adding Outputs

Host	The destination host for the stream.
Port	Specify the ports to listen on for TCP streams. Default: 7777.
HTTP	If the target is an HTTP server, select the HTTP checkbox. In this case, HTTP headers will be added to the stream.
Multi Path TCP	Select this checkbox to enable MultiPath TCP, which enables the transmission of a stream over TCP using two network interfaces (e.g. Wifi + mobile). Multi Path TCP is available for Linux only.
Mode	<p>The multiple links can be configured to:</p> <ul style="list-style-type: none">• Aggregate - aggregate the bandwidth of the multiple links in order to use the total capacity of both links. In this case ZEC will use all available bandwidth among all available flows (if needed) to send the stream.• Duplicate - enhance the path's resiliency by duplicating the stream and sending through multiple links in order to overcome errors and packet loss.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable Decryption	Select this checkbox to enable decryption of an encrypted stream.
Decryption type	<p>If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used.</p> <p>Select Automatic to decrypt a stream that has been encrypted using Automatic encryption.</p> <p>Only if the stream has not been encrypted, select None (default).</p> <p>Important Notice: if the stream has been encrypted you must decrypt it in the output.</p>

ZEC Outputs

Adding Outputs

Decryption key	Enter the decryption key to decrypt the encrypted stream.
-----------------------	---

Adding HTTP Push Outputs

The HTTP Push output stream can be encapsulated in HLS or DASH. The source of the output stream is a predefined adaptive group that has been configured in the **Adaptive Groups** screen. The configuration of the stream includes the option to delete outdated stream fragments on the server. SCTE-35 markers in the source input will be preserved and used to segment the stream for both HLS and DASH encapsulation. Output streams can be pushed to one ZEC instance.

The path to the destination can be formed in one of the following ways:

- **Full path** – in this option the path would be constructed as follows: `<base url>/<path>/<file>?<additional params may be also with path and file>`
- **Path in parameters** - in this option the path would be constructed as follows: `<base url>?<additional params may be also with path and file>`
- **Flat path** - in this option the path would be constructed as follows: `<base url>/<path>_<file>?<additional params may be also with path and file>`. Any "/" in path should be replaced with "_"

Low Latency HLS - ZEC supports low latency HLS delivery using chunked transfer encoding, which starts sending an HTTP response as chunks of data when they are ready before the complete response is available. Chunked transfer encoding can be used with transport stream (TS) segments and with fragmented MP4 (fMP4). For low latency HLS and DASH, ZEC must be used as an origin server. To enable low latency HLS and DASH, select **Enable HLS Fast playback** on **Settings > Live Protocols** screen.

ZEC Outputs

Adding Outputs

➔ To Create an HTTP Push Output:

1. In the ZEC **Outputs** page, click **+ New Output**.
The **New Output** window is displayed.

2. Select the **HTTP Push** option (radio button).
3. Type in the unique identifier for this output stream in the **Output Name**.
4. Select an **Input Adaptive Group** to be made available on this output from the adjacent drop-down list. To create an Adaptive Group, see [Adaptive Groups](#).
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: not selected.
6. Enter the **Output Parameters** (see Output Stream Parameters Table).
7. If your destination server requires authorization credentials to connect, select the **Authorization** checkbox (see Output Stream Parameter Table below).
8. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameter Table below).
9. Click OK.
The new HTTP Push Output with its settings is created and now appears on the screen.

ZEC Outputs

Adding Outputs

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Encapsulation Options	<ul style="list-style-type: none">HLS Encapsulation - the output stream, which includes all the streams in the selected Adaptive group, will be encapsulated in HTTP Live Streaming format.Dash Encapsulation - the output stream, which includes all the streams in the selected Adaptive group, will be encapsulated in MPEG DASH format.
Depending on the selection in the Segment Path field below, this field should include the following:	
Target URL	<ul style="list-style-type: none">Full path – <code><base url>/<path>/<file></code>Path in parameters - in this option the path would be constructed as follows: <code><base url></code>Flat path - in this option the path would be constructed as follows: <code><base url>/<path>_<file></code>
Depending on the selection in the Segment Path field below, this field should include the following:	
Additional URL parameters	<ul style="list-style-type: none">Full path – <code>?<additional params may be also with path and file></code>Path in parameters - <code>?<additional params may be also with path and file></code>Flat path - <code>?<additional params may be also with path and file></code>. Any "/" in path should be replaced with "_" <p>URL parameters support macros as follows:</p> <ul style="list-style-type: none"><code>%PATH%</code> - file path as it appears in the playlist<code>%FILE%</code> - file name
Delete outdated stream fragments on server	Select this checkbox to delete any outdated stream fragments from the server.
Upload DVR playlist	Select this checkbox if you are streaming a recorded/VOD stream and you want to upload a DVR playlist in addition to the live playlist.

ZEC Outputs

Adding Outputs

Select one of the following path segmentation types:

Segment Path	<ul style="list-style-type: none">• Full path – in this option the path would be constructed as follows: <code><base url>/<path>/<file>?<additional params may be also with path and file></code>• Path in parameters - in this option the path would be constructed as follows: <code><base url>?<additional params may be also with path and file></code>• Flat path - in this option the path would be constructed as follows: <code><base url>/<path>_<file>?<additional params may be also with path and file></code>. Any "/" in path should be replaced with "_"
Ignore TLS certificate errors	Select this option when streaming to a trusted server that does not have a valid certificate. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Authorization	Select this checkbox if your destination server requires authorization credentials to connect.

Select one of the following authorization methods:

Method	<ul style="list-style-type: none">• Basic authorization• Digest authorization• OAuth2 authorization
---------------	---

Username	Type the username
Password	Type the password
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.

ZEC Outputs

Adding Outputs

Adding AWS Outputs

The HTTP output stream, which is encapsulated in HLS or DASH/fMP4 HLS can be pushed to either an AWS S3 Bucket or to an AWS Elemental MediaStore. The native AWS support includes the ability to configure the S3 authentication credential, including the Region, Access Key, and Secret Key.

➔ To Create an AWS Output:

1. In the **ZEC Outputs** page, click **+ New Output**. The **New Output** window is displayed.

2. Select the **AWS** option (radio button).
3. Type in the unique identifier for this output stream in the **Output Name**.
4. Select an **Input Adaptive Group** to be made available on this output from the adjacent drop-down list. To create an Adaptive Group, see [Adaptive Groups](#).
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: not selected.
6. Enter the **Output Parameters** (see Output Stream Parameters Table).
7. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameter Table below).
8. Click **OK**.

The new AWS Output with its settings is created and now appears on the screen.

ZEC Outputs

Adding Outputs

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Service	Select one of the following options: <ul style="list-style-type: none">• S3 Bucket - the output stream will be pushed to the specified S3 Bucket.• Elemental Media Store - the output stream will be pushed to the specified AWS Elemental MediaStore.
Encapsulation	<ul style="list-style-type: none">• HLS Encapsulation - the output stream, which includes all the streams in the selected Adaptive group, will be encapsulated in HTTP Live Streaming format.• Dash Encapsulation - the output stream, which includes all the streams in the selected Adaptive group, will be encapsulated in MPEG DASH format.
URL	<p>The URL address of the destination host for the S3 Bucket or the AWS Elemental MediaStore.</p> <p>The path to the destination can be formed in one of the following ways according to the option selected in the Segment Path field below:</p> <ul style="list-style-type: none">• Full path – in this option the path would be constructed as follows: <code><base url>/<path>/<file>?<additional params may be also with path and file></code>• Path in parameters - in this option the path would be constructed as follows: <code><base url>?<additional params may be also with path and file></code>• Flat path - in this option the path would be constructed as follows: <code><base url>/<path>_<file>?<additional params may be also with path and file></code>. Any "/" in path should be replaced with "_"
Delete outdated stream fragments on server	Select this checkbox to send delete messages to S3/AWS Elemental MediaStore to delete the outdated stream fragments from the servers.
Ignore TLS certificate errors	Select this option when streaming to a trusted server that does not have a valid certificate. When this option is selected, ZEC will ignore the TLS certificate errors and transmit the stream to its destination.
Access key	Enter your AWS S3 or AWS Elemental MediaStore Access key.
Secret key	Enter your AWS S3 or AWS Elemental MediaStore Secret key.

ZEC Outputs

Adding Outputs

Select one of the following path segmentation types:

Segment Path

- **Full path** – in this option the path would be constructed as follows: <base url>/<path>/<file>?<additional params may be also with path and file>
- **Path in parameters** - in this option the path would be constructed as follows: <base url>?<additional params may be also with path and file>
- **Flat path** - in this option the path would be constructed as follows: <base url>/<path>_<file>?<additional params may be also with path and file>. Any "/" in path should be replaced with "_"

Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.


Adding SRT Outputs

The SRT output can be pulled to/from an SRT-enabled device and is configured via Zen Master or Zixi API only. SRT stands for 'Secure Reliable Transport' and is an open-source video transport protocol and technology stack. SRT uses secure streams and easy firewall traversal to optimize streaming performance and deliver high-quality video over even the most unreliable networks.

The other connection on the stream must be connected to Zixi Broadcaster or AWS MediaConnect.

➔ To Create an SRT Output:

10. In the ZEC **Outputs** page, click **+ New Output**. The **New Output** window is displayed.



11. Type in the unique identifier for this output in the **Output Name**.
12. Select an **Input Stream** to be made available on this output from the drop-down list.
13. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
14. Select **SRT**.
15. Enter the **Output Parameters** (see Output Stream Parameters Table).
16. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameters Table below).
17. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see [Decrypting an Output Stream in ZEC](#).
18. Click **OK**.

The new SRT Output with its settings is created and now appears on the screen.

ZEC Outputs

Adding Outputs

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Listening Port	Specify the port to listen on. This port must be open on all firewalls between the ZEC and other devices it is communicating with.
Password	If the stream is password protected, enter the password.
Latency	Specify the maximum latency of the stream in milliseconds. Default: 1000
Encryption Type	Specify the type of Encryption (AES 128/192/256).
Bind to IP	Select from the drop-down list the local IP address to be used for this output, OR select <i>Any</i> to enable any IP to be used.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable Decryption	Select this checkbox to decrypt an encrypted stream.
Decryption type	<p>If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used.</p> <p>Select Automatic to decrypt a stream that has been encrypted using Automatic encryption.</p> <p>Only if the stream has not been encrypted, select None (default).</p> <p>Important Notice: if the stream has been encrypted you must decrypt it in the output.</p>
Decryption key	If the decryption type includes a key, enter the key to decrypt the stream during output.

Adding SRT Client Outputs

The SRT Client output can be pushed to an SRT-enabled device and is configured via Zen Master or Zixi API only. SRT stands for 'Secure Reliable Transport' and is an open-source video transport protocol and technology stack. SRT uses secure streams and easy firewall traversal to optimize streaming performance and deliver high-quality video over even the most unreliable networks.

➔ To Create an SRT Client Output:

10. In the ZEC **Outputs** page, click **+ New Output**. The **New Output** window is displayed.

The screenshot shows the 'New Output' configuration window. The window title is 'New output'. The navigation bar includes 'OUTPUTS', 'ADAPTIVE', 'VOD', 'SETTINGS', 'EVENT LOG', and 'MATRIX'. The 'OUTPUTS' tab is selected. The form fields are: 'Output Name:' (text input), 'Input Stream:' (dropdown menu), 'Show in Matrix:' (checked checkbox), a radio button group for output protocols (UDP, RTMP, Push, TCP, HTTP Push, AWS, SRT, SRT Client, RIST) with 'SRT Client' selected, an 'Output parameters' section with fields for Host, Port, Password[10-80], Latency[ms] (set to 1000), Encryption type (set to None), and Bind to IP (set to Any), a 'Billing Codes' checkbox, and an 'Enable decryption' checkbox. 'Ok' and 'Cancel' buttons are at the bottom right.

11. Type in the unique identifier for this output in the **Output Name**.

12. Select an **Input Stream** to be made available on this output from the drop-down list.

13. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.

14. Select **SRT Client**.

15. Enter the **Output Parameters** (see Output Stream Parameters Table).

16. If you want to specify **Billing Codes** to identify and differentiate traffic for billing purposes, select this checkbox (see Output Stream Parameters Table below)

17. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see [Decrypting an Output Stream in ZEC](#).

18. Click **OK**.

The new SRT Client Output with its settings is created and now appears on the screen.

ZEC Outputs

Adding Outputs

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Host	The destination host for the SRT stream.
Port	Specify the ports to which the stream will be pushed.
Password	If the stream is password protected, enter the password.
Latency	Specify the maximum latency of the stream in milliseconds. Default: 1000
Encryption Type	Specify the maximum expected bitrate for memory allocation. Recommended: 2X the actual bitrate, which will prevent buffer overruns (especially with VBR streams). Default: 8000. Note – Overflows will typically occur when the Max Bitrate isn't sufficient.
Bind to IP	Select from the drop-down list the local IP address to be used for this output, OR select <i>Any</i> to enable any IP to be used.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable Decryption	Select this checkbox to decrypt an encrypted stream.
Decryption type	If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used. Select Automatic to decrypt a stream that has been encrypted using Automatic encryption. Only if the stream has not been encrypted, select None (default). Important Notice: if the stream has been encrypted you must decrypt it in the output.
Decryption key	If the decryption type includes a key, enter the key to decrypt the stream during output.

Adding RIST Outputs

The RIST output can be push streams or have them pulled to/from a RIST-enabled device. RIST seeks to provide reliable, high performance media transport by using UDP at the transport layer to avoid the inefficiencies of TCP, then layering on top Forward Error Correction and Retransmits to add the reliability inherently absent from UDP.

ZEC supports the following RIST profiles:

- **Simple Profile (PUSH only)** - The RIST Simple Profile provides best-in-class packet protection, as well as support for multi-link bonding and seamless switching.
- **Main Profile (PUSH/PULL)** – The RIST Main Profile builds upon the features of the Simple Profile to provide backwards compatibility, while opening the door for additional features, including:
 - **Encryption and authentication** - RIST Main Profile uses industry-standard DTLS or PSK with a variety of available cyphers to ensure the most up-to-date protection, while being flexible to accommodate local legal regulations. Support for pre-shared keys is also included, which makes RIST Main Profile compatible with one-to-many environments such as satellite or multicast distribution.
 - **Native tunneling and multiplexing** - the ability to combine multiple Simple Profile RIST streams into one single connection, optionally with one single encryption and authentication step, using industry-standard GRE over UDP.
 - **Bandwidth optimization** - by deleting NULL packets at the source and re-inserting them at the destination.
 - **Support for high bit rate streams** - The RIST Main Profile includes an RTP header extension which increases the sequence number size to 32-bits, and therefore increases the maximum size of retransmission buffers, and thus opens the door for higher bitrate streams, such as lightly compressed (e.g. JPEG 2000, Tico) and uncompressed video.

Contact your ZEC representative to learn more about interoperability testing between ZEC and 3rd party devices. More details about RIST can be found at www.rist.tv

ZEC Outputs

Adding Outputs

➔ To Add a RIST Output:

1. In the ZEC **Outputs** page, click **+ New Output**. The **New Output** window is displayed.

The screenshot shows the 'New Output' dialog box. The 'RIST' radio button is selected. The 'Output Name' field is empty. The 'Input Stream' dropdown is open. The 'Show in Matrix' checkbox is unchecked. The 'Output parameters' section includes: Profile (Simple Profile), Host (empty), Port (empty), Smoothing [ms] (0), SMPTE-2022 FEC (Disable), Bind to IP (Any), and Local port (empty). The 'Billing Codes', 'Remultiplex/Pad', 'Enable decryption', and 'Enable IFB/Talkback' checkboxes are all unchecked. The 'Ok' and 'Cancel' buttons are visible at the bottom right.

2. Select the **RIST** option (radio button).
3. Type in the unique identifier for this output stream in the **Output Name**.
4. Select an **Input Stream** to be made available on this output from the adjacent drop-down list.
5. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: not selected.
6. Enter the **Output Parameters** (see Output Stream Parameters Table).
7. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameter Table below).
8. If you want to remux the stream to CBR (used for professional IRDs) in order to avoid bandwidth waste or add NULL packets and adjust the stream clock (PCR) in order to make the stream CBR, select Remultiplex/Pad and configure the respective parameters (see Output Stream Parameters Table).
9. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see [Decrypting an Output Stream in ZEC](#).
10. Click **OK**.
The new RIST Output with its settings is created and now appears on the Outputs screen.

ZEC Outputs

Adding Outputs

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Profile	Select one of the following RIST profiles that matches the input stream: <ul style="list-style-type: none">• Simple Profile (default)• Main Profile
Type (Main Profile)	Select the stream direction: <ul style="list-style-type: none">• Push• Pull
Host	Specify the destination IP address or URL of the host to which the steam will be pushed.
Port	Specify the target UDP port.
TTL	Specify the time-to-live (TTL). Used mainly to limit the range (or “scope”) of a multicast transmission. Leaving it as blank uses the default value specified by the operating system
Smoothing [ms]	Enables transmission of the output at the correct rate. Required when the receiving device is sensitive and can’t lock on to the stream (in such a case, the recommended latency is 100 - 1000 ms)

ZEC Outputs

Adding Outputs

In the SMPTE-2022 FEC standard, 1-D and 2-D parity codes are systematic FEC codes of decent complexity that provide protection against bursty or random losses.



This setting can be modified without interrupting an existing stream.

SMPTE-2022 FEC

To enable SMPTE-2022 FEC (Forward Error Correction) select one of the following parity options from the drop-down menu:

- **1D** - SMPTE-2022 1D can fix a problem in ONE packet per row. This means that the number of rows specified should consider the packet loss rate- the shorter the row, the more error resilience can be achieved on the expense of bitrate level. However, longer rows increase the delay that the FEC will add. It is recommended to select this option when the packet loss is sporadic.
The stream will occupy the source port and two ports above it (e.g. if the source port is 8988, it will occupy 8990).
- **2D** - SMPTE-2022 2D uses a table of packets, which includes rows and columns. This option is more error resilient, but it increases the delay by (row*column) packets and increases the bitrate with R+C packets per each table of R*C packets. It is recommended to select this option when packet loss is bursty.
The stream will occupy four ports above (e.g. if the source port is 8988, it will occupy 8992).

Bind to IP

Select from the drop-down list the local IP address to be used for this Input, OR select *Any* to enable any IP to be used.

Local Port

Specify from which local port to source the stream, if desired (instead of randomly chosen by the operating system).

Billing Codes

Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.

Billing Code

Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.

Billing password

Enter the password that corresponds to this billing code.

RIST main profile parameters

Use DTLS

Select this checkbox to encrypt the stream dynamically using DTLS.

ZEC Outputs

Adding Outputs


Remultiplex/Pad	Select this checkbox to enable remuxing from VBR MPEG-TS to MPEG-TS CBR (used for professional IRDs) or padding with null packets.
Mode	Select one of the following: <ul style="list-style-type: none">• Pad – adds NULL packets and adjusts the stream clock (PCR) in order to make the stream CBR.• Remultiplex - performs demux->mux and rebuilds the stream according to the below parameters.
Target bitrate [kbps]:	Specify the CBR bitrate to target for a remuxed stream.
Buffer Size [ms]	Specify the size of the buffer that will be used for the remuxing. A larger buffer increases the quality, but also increases latency.
No NULL Packets	Select this option to re-multiplex the stream to CBR but remove the NULL packets in order to maintain low bitrate.
Enable Decryption	Select this checkbox to decrypt an encrypted stream.
Decryption type	<p>If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used.</p> <p>Select Automatic to decrypt a stream that has been encrypted using Automatic encryption.</p> <p>Only if the stream has not been encrypted, select None (default).</p> <p>Important Notice: if the stream has been encrypted you must decrypt it in the output.</p>
Decryption key	If the decryption type includes a key, enter the key to decrypt the stream during output.
Enable IFB/Talkback	Select this checkbox to enable IFB/Talkback for one-way communication from the director or assistant director to on-air talent or a remote location. Selecting the checkbox allows the ZEC decoder to send audio back to the ZEC encoder. This offers the ability to, for example, give audio feedback to the camera operator.
Port	The port that will be used to send the audio feedback.

ZEC Outputs

Viewing Existing Outputs

Viewing Existing Outputs

The Outputs screen displays all the output streams that have been created.



The screenshot shows the 'Outputs' screen in a web application. At the top, there is a navigation bar with tabs for STATUS, INPUTS, OUTPUTS (selected), ADAPTIVE, VOD, SETTINGS, EVENT LOG, and MATRIX. A LOGOUT button is on the right. Below the navigation bar is a search box labeled 'Search Outputs' and buttons for '+ New Output' and 'Reload'. The main content is a table with the following columns: Status, Name, Type, Destination, Bitrate[kbps], Uptime, Latency, Input ID, and Actions. The table contains four rows of data, all with a 'Connected' status (indicated by a green circle icon).

Status	Name	Type	Destination	Bitrate[kbps]	Uptime	Latency	Input ID	Actions
Connected	alon_push_zec_1	Push	QA-Gil-Alon-Tech-Writer-ij95@172.31.35.108	971	165:14:28	4000	alon_ZEC_source	[Icon] [Icon]
Connected	alon_ZEC_udp_1	UDP	172.31.35.108:5555	1000	165:13:23	0	alon_ZEC_source	[Icon] [Icon]
Connected	alon_ZEC_udp_2	UDP	172.31.35.108:5575	1000	165:13:02	0	alon_ZEC_source	[Icon] [Icon]
Connected	HLS:0	HTTP	127.0.0.1	985	165:12:00	0	HLS:adaptive/alon_ZE...	[Icon] [Icon]

Hovering the cursor on the status indicator of a stream shows the stream configuration information and basic utilization statistics, where applicable.

Any of the columns in the following table can be sorted in ascending/descending order by clicking on its heading. The **Search** text box in the upper left-hand side of the screen can be used to search for a specific input stream by entering the desired Stream ID.


Field	Description
Status	Displays the status of output stream. The following colored indicators are displayed: <ul style="list-style-type: none">• Green = Connected• Yellow = Connecting• Red = Disconnected with an error condition• Blue = Offline with no connection attempts• Grey = Offline and stopped
Name	Displays the name of the output stream, as defined in ZEC.
Type	Displays the type of output stream.
Destination	Displays the IP address of the host that will be receiving the stream.
Bitrate [kbps]	Displays bitrate of the connected output stream.
Uptime	Displays the amount of time the stream has been active.
Latency	Displays the configured latency
Input ID	The ID of the related Input stream.
Actions	Provides access to various actions to be performed on this output stream (see Performing Actions on Output Streams below).


ZEC Outputs

Viewing Existing Outputs

Stats Pane

The Stats pane on the bottom of the page shows data about the activity of the selected stream.



Click the  icon next to a parameter to show the graph of historical data for the specified parameter.

Field	Description
Bitrate (kbps)	Displays the current bitrate of the output stream
Up Time	Displays the amount of time the stream has been active.
Last Connected	Displays the date and time in which the stream was connected.
Send Errors	Displays the number of errors generated after sending the stream.
Reconnections	Displays the number of reconnection attempts.
RTT (ms)	Displays the Round Trip Time (RTT) from the source (in milliseconds)
Jitter	Displays the current Jitter, measured in milliseconds.
Congestion [%]	Displays an estimation of the communication's congestion level – '0' means congestion free, '100' means fully congested.
Total Packets	Displays the total number of packets that have been transmitted.
Packet Rate	Displays the current number of packets per second.
Packet Loss %	Displays the packet loss rate (how many packets were lost out of the total number of packets).
Remuxing Resets	The number of packets that were dropped in a row. Consecutive packets dropped could imply burst loss, as opposed to a sustained percentage of loss, which would imply congestion.
Remuxing Overflows	This indicates that the multiplexer internal queues are full.
Smoother Violations	N/A
Consecutive Drops	The number of packets that were dropped in a row. When consecutive packets are dropped that could imply burst loss, as opposed to a sustained % of loss that would imply congestion.


ZEC Outputs

Viewing Existing Outputs

Dropped Packets	Displays the total number of packets that were dropped since the beginning of the stream.
Recovered Packets	Displays the total number of dropped packets that have been recovered since the beginning of the stream.
Not Recovered Packets	Displays the number of non-recovered packets.
Failed Sends	Displays the number of failed attempts to send the stream.
FEC Packets	Displays the number of FEC packets transmitted.
FEC Recovered	Displays the number of FEC packets that were recovered.
ARQ Requests	Displays the number of requests for transmission of dropped packets made with ARQ.
ARQ Recovered	Displays the number of dropped packets recovered via ARQ.
ARQ Duplicates	Displays the number of duplicate recovery packets received via ARQ.
ARQ Ignored	Displays the number of dropped packets made with ARQ that were ignored.
Overflows	Displays the number of packets lost due to buffer overflow. Note: overflow is usually the result of the Max Bitrate being too low.

Searching for Output Streams

➔ To Search for an Output Stream:

In the ZEC **Outputs** page, type in the specific output stream name in the search text box on the left-hand top of the screen and click . The **Output** screen displays the requested output stream(s).

Performing Actions on Output Streams


Every stream has a shortcut button that can be used to perform relevant actions on the stream. The following actions can be performed through the Actions button:

- [Stopping/Starting the Input Stream](#)
- [Editing Output Settings or Duplicating Output Streams](#)
- [Deleting Output Streams from ZEC](#)
- [Switching Input](#)
- [Viewing Traceroutes](#)

Stopping/Starting the Input Stream


You can start or stop the output stream at any time.

➔ To Stop/Start the Output Stream:

1. On the **Outputs** page of ZEC, click the desired row of the output stream that you want to stop.
2. Click the  button on the right end of the selected row and then **Stop**. The selected row which was a Connected Output Stream is no longer displayed and appears below as **Offline**.
3. To continue the Output Stream click **Start** from the same menu.

Editing Output Settings or Duplicating Output Streams


➔ To Edit the Configuration of an Output Stream:

1. In the ZEC **Outputs** page, click the desired output stream that you want to edit.
2. Click the  button on the right end of the selected row and then **Edit**. The **Edit output stream name** window is displayed. You can modify any of the settings.
3. Click **OK**. The new settings will take effect.

ZEC Outputs


Performing Actions on Output Streams

➔ To Duplicate the Configuration of an Output Stream:

1. In ZEC **Outputs** page, click the desired output stream that you want to duplicate.
2. Click the  button on the right end of the selected row and then **Duplicate**. The **Duplicate output stream name** window with the settings of the original output stream is displayed. You can modify any of these settings.
3. Click **OK**. The duplicate output stream with its new settings will be created.


Deleting Output Streams from ZEC

➔ To Delete an Output Stream from the ZEC:

1. In the ZEC **Outputs** page, select the output stream you want to delete, and then click .
2. Click **Delete** to the selected stream. The selected input stream was deleted and is not displayed anymore.

Switching Input


➔ To change the input associated with the selected output:

1. In the ZEC **Outputs** page, click  and select **Switch Input**. The **Switch source** window is displayed.
2. In the **New Input** drop-down, select the desired input, and click **OK**. The newly designated input is now associated with the selected output.

Viewing Traceroutes

You can view traceroute data for a stream sent from Zixi.

➔ To view traceroute data:


1. On the **Outputs** page of ZEC, click on the row of the stream for which you want to view traceroutes.
2. Click the  button on the right end of the selected row and then select **Trace**.

Performing Actions on Multiple Outputs

Start and Stop Marked Individual and Multiple Outgoing Streams

➔ To Stop/Start Output Streams:

1. In the **ZEC Outputs** page, select all outputs by selecting the **Actions** checkbox, located in the header line, or select individual outputs by selecting their checkboxes. The Marked drop-down button is displayed.




2. Click the **Marked** drop-down menu and then click **Start/Stop**. The selected Output Streams are started/stopped.

Toggle Output Stream Records

➔ To Toggle Output Stream Records:

1. In the **ZEC Outputs** screen, select the relevant outputs by selecting their checkboxes. The Marked drop-down button is displayed.




2. Click the Marked drop-down menu and then click Toggle Record.
3. The output streams are toggled.

Delete Marked Individual and Multiple Outgoing Stream

➔ To Delete Output Streams:

1. In the **ZEC Outputs** page, select all outputs by selecting the checking the **Actions** checkbox at the header line, or select individual outputs by selecting their checkboxes. The Marked drop-down button is displayed.




2. Click the **Marked** drop-down menu and then click **Delete**. The selected Output Streams are deleted.

Save Marked Individual and Multiple Outgoing Streams

➔ To Save Output Streams:

1. In the **ZEC Outputs** page, select all outputs by selecting the **Actions** checkbox, located in the header line, or select individual outputs by selecting their checkboxes. The Marked drop-down button is displayed.



ZEC Outputs

Performing Actions on Multiple Outputs

2. Click the **Marked** drop-down menu and then click **Save**.
The selected Output Streams are saved.

Reset Stats for Individual and Multiple Outgoing Streams

➔ To Reset Output Streams:

1. In the ZEC Outputs page, select all outputs by selecting the **Actions** checkbox, located in the header line, or select individual outputs by selecting their checkboxes. The **Marked** drop-down button is displayed.



2. Click the **Marked** drop-down menu and then click **Reset**.
The selected Output Streams are reset.

Decrypting an Output Stream in ZEC

Any stream that has been encrypted using standard AES static key can be decrypted in ZEC. You can configure the decryption of a specific stream by entering the decryption key.

➔ To decrypt an output stream in ZEC:

8. In **Outputs** screen, click **+New Output**.
9. Select **UDP**, **RTMP**, **TCP**, **SRT**, **SRT Client** or **RIST**.
10. Fill in the output details.
11. At the bottom, select the **Enable decryption** checkbox.
12. In the **Decryption type** field, select **AES 128**, **AES 192**, **AES 256** for fixed key.
13. In the **Decryption Key** field, enter the exact same key that was used to encrypt the stream.

The screenshot shows the 'New output' configuration dialog in ZEC. The dialog has a title bar with a close button (X). Below the title bar, there are several input fields: 'Output Name' (text box), 'Input Stream' (dropdown menu), and 'Show in Matrix' (checkbox, checked). Below these fields, there are radio buttons for selecting the output type: UDP (selected), RTMP, Push, TCP, HTTP Push, AWS, SRT, SRT Client, and RIST. Below the radio buttons, there is a section titled 'Output parameters' with several input fields: 'Host' (text box), 'Port' (text box), 'TTL' (text box), 'Smoothing [ms]' (text box, value 0), 'RTP' (checkbox, unchecked), 'Bind to IP' (dropdown menu, value Any), and 'Local port' (text box). Below the 'Output parameters' section, there are three checkboxes: 'Billing Codes' (unchecked), 'Remultiplex/Pad' (unchecked), and 'Enable decryption' (checked). Below the 'Enable decryption' checkbox, there are two fields: 'Decryption type' (dropdown menu, value AES 128) and 'Decryption key' (text box). Below the 'Decryption key' field, there is a checkbox for 'Enable IFB/Talkback' (unchecked). At the bottom right of the dialog, there are two buttons: 'Ok' and 'Cancel'.

14. Click **OK**.


Using Output Templates

Instead of manually creating an output and then connecting the output to an input, you can define output templates with rules for automatic creation of outputs with predefined settings. The template includes an Input pattern. When an input pattern matches the pattern of an incoming input stream, the output is created automatically.

➔ To create a new Output template:


1. Click the **Outputs** tab at the top of the ZEC administrative screen.
2. In the **Menu** bar, click the **Templates** () button.

The **Output Templates** window is displayed:



3. Under **Input ID Parameters**, click the '+' button.

The **New Output Pattern Template** window is displayed:




4. In the **Input ID Pattern** field, enter a pattern for the Stream ID of the input stream for which an output will be automatically created. This pattern will be used to identify the input stream and can include variables that are marked with the "\$" sign followed by a number (e.g. \$1, \$2, etc.) and/or with an asterisk "*" wildcard.

The patterns should also include a part of the string that requires an exact match.

For example, the pattern "\$1_stream_\$2kbps" will match an input stream "talk_show_stream_600kbps".

5. Click **Apply**.
The newly created input ID pattern is added to the **Input ID Patterns** list.
6. From the **Input ID Patterns** list, select a pattern for which you want to relate an output template.

7. In the **Output Template Description** section click the “+” button.



The **New Output Template** window is displayed:

New output template

Input ID Pattern:
The pattern will be matched against inputs.
Parts of input stream ids can be assigned to variables ["\$1" .. "\$9"].
* can be used as wild card.
e.g. \$1_stream_*

Output Name:

Show in Matrix:

UDP RTMP Push TCP HTTP Push AWS SRT SRT Client RIST

Output parameters

Host:

Port: TTL:

Smoothing [ms]:

RTP:

Bind to IP:

Local port:

Billing Codes

Remultiplex/Pad

Enable decryption

Enable IFB/Talkback

8. In the **Output Name** field, enter a name for the output that will be created. The name can include variables used in the **Input Pattern** field. For example, the pattern "*\$1_ouput_stream_\$2kps*" will eventually create an output "*talk_show_output_stream_600kbps*", as it uses the variables that were defined in the **Input Pattern** field.
9. Select the desired output type and fill-in the relevant Output parameters according to the instructions of the relevant section:
 - **UDP Output** – Follow the instructions in the [Adding UDP Outputs](#) section.
 - **RTMP Output** – Follow the instruction in the [Adding RTMP and RTMPS Outputs](#) section.
 - **Pull Output** - Follow the instruction in the [Error! Reference source not found.](#) section.
 - **Push Output** - Follow the instruction in the [Adding Push Outputs](#) section.

ZEC Outputs

Using Output Templates

- **TCP Output** - Follow the instruction in the **Adding TCP Outputs** section.
- **HTTP Push** - Follow the instructions in the **Adding HTTP Push Outputs** section. Note that the **Target URL** field can also use the same variables used in the **Input Pattern** field. For example, "[https://s3.amazonaws.com/zixi/\\$1_folder_\\$2kbps](https://s3.amazonaws.com/zixi/$1_folder_$2kbps)".
- **AWS Output** - Follow the instructions in the **Adding AWS Outputs** section. Note that the **URL** field can also use the same variables used in the **Input Pattern** field. For example, "[https://s3.amazonaws.com/zixi/\\$1_folder_\\$2kbps](https://s3.amazonaws.com/zixi/$1_folder_$2kbps)".
- **RIST Output** – Follow the instruction in the **Adding SRT Outputs**

The SRT output can be pulled to/from an SRT-enabled device and is configured via Zen Master or Zixi API only. SRT stands for 'Secure Reliable Transport' and is an open-source video transport protocol and technology stack. SRT uses secure streams and easy firewall traversal to optimize streaming performance and deliver high-quality video over even the most unreliable networks.

The other connection on the stream must be connected to Zixi Broadcaster or AWS MediaConnect.

➔ To Create an SRT Output:

19. In the ZEC **Outputs** page, click **+ New Output**. The **New Output** window is displayed.

The screenshot shows the 'New output' configuration window. The 'Output Name' field is empty. The 'Input Stream' dropdown is set to a default value. The 'Show in Matrix' checkbox is checked. The output type is set to 'SRT'. The 'Output parameters' section includes: 'Listening Port' (empty), 'Password[10-80]' (empty), 'Latency[ms]' (1000), 'Encryption type' (None), and 'Bind to IP' (Any). The 'Billing Codes' and 'Enable decryption' checkboxes are unchecked. The 'Ok' and 'Cancel' buttons are visible at the bottom right.

20. Type in the unique identifier for this output in the **Output Name**.
21. Select an **Input Stream** to be made available on this output from the drop-down list.
22. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.
23. Select **SRT**.
24. Enter the **Output Parameters** (see Output Stream Parameters Table).

ZEC Outputs

Using Output Templates

25. If you want to specify **Billing Codes** to identify and differentiate traffic on a ZEC for billing purposes, select this checkbox (see Output Stream Parameters Table below).
26. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see Decrypting an Output Stream in ZEC.
27. Click **OK**.

The new SRT Output with its settings is created and now appears on the screen.

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Listening Port	Specify the port to listen on. This port must be open on all firewalls between the ZEC and other devices it is communicating with.
Password	If the stream is password protected, enter the password.
Latency	Specify the maximum latency of the stream in milliseconds. Default: 1000
Encryption Type	Specify the type of Encryption (AES 128/192/256).
Bind to IP	Select from the drop-down list the local IP address to be used for this output, OR select <i>Any</i> to enable any IP to be used.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable Decryption	Select this checkbox to decrypt an encrypted stream.
Decryption type	If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used.

ZEC Outputs

Using Output Templates

Select **Automatic** to decrypt a stream that has been encrypted using **Automatic** encryption.

Only if the stream has not been encrypted, select **None** (default).

Important Notice: if the stream has been encrypted you must decrypt it in the output.

Decryption key


If the decryption type includes a key, enter the key to decrypt the stream during output.

Adding SRT Client Outputs

The SRT Client output can be pushed to an SRT-enabled device and is configured via Zen Master or Zixi API only. SRT stands for 'Secure Reliable Transport' and is an open-source video transport protocol and technology stack. SRT uses secure streams and easy firewall traversal to optimize streaming performance and deliver high-quality video over even the most unreliable networks.

➔ To Create an SRT Client Output:

19. In the ZEC **Outputs** page, click **+ New Output**. The **New Output** window is displayed.



20. Type in the unique identifier for this output in the **Output Name**.

21. Select an **Input Stream** to be made available on this output from the drop-down list.

22. Select the **Show in Matrix** check box to display this stream in the Matrix (see [Using the Matrix](#)). Default: Selected.

23. Select **SRT Client**.

24. Enter the **Output Parameters** (see Output Stream Parameters Table).

ZEC Outputs

Using Output Templates

25. If you want to specify **Billing Codes** to identify and differentiate traffic for billing purposes, select this checkbox (see Output Stream Parameters Table below)
26. You can decrypt an encrypted stream as it enters the ZEC. To decrypt a stream, select the **Decrypt Stream** checkbox and fill in the parameters as described in the Output Stream Parameter Table below. For more information, see Decrypting an Output Stream in ZEC.
27. Click **OK**.

The new SRT Client Output with its settings is created and now appears on the screen.

Output Stream Parameters Table

Parameter	Description
Output Parameters	
Host	The destination host for the SRT stream.
Port	Specify the ports to which the stream will be pushed.
Password	If the stream is password protected, enter the password.
Latency	Specify the maximum latency of the stream in milliseconds. Default: 1000
Encryption Type	Specify the maximum expected bitrate for memory allocation. Recommended: 2X the actual bitrate, which will prevent buffer overruns (especially with VBR streams). Default: 8000. Note – Overflows will typically occur when the Max Bitrate isn't sufficient.
Bind to IP	Select from the drop-down list the local IP address to be used for this output, OR select <i>Any</i> to enable any IP to be used.
Billing Codes	Billing codes are used to identify and differentiate traffic on a ZEC for billing purposes. When a billing code is added to a Source or Target, ZEC can track the traffic on that ZEC input or output separately from other inputs and outputs on the same ZEC. Billing codes are created by ZEC personnel on the ZEC Customer Portal for a particular organization.
Billing Code	Enter the billing code that corresponds to this stream. The relevant billing can be obtained from the organization that received the billing code from Zixi.
Billing password	Enter the password that corresponds to this billing code.
Enable Decryption	Select this checkbox to decrypt an encrypted stream.

ZEC Outputs

Using Output Templates

If the stream has been encrypted, you can decrypt through the output by selecting this checkbox and specifying the type of encryption that was used.

Decryption type Select **Automatic** to decrypt a stream that has been encrypted using **Automatic** encryption.

Only if the stream has not been encrypted, select **None** (default).

Important Notice: if the stream has been encrypted you must decrypt it in the output.

Decryption key If the decryption type includes a key, enter the key to decrypt the stream during output.

- Adding RIST Outputs section.
10. Click **OK**.
- The template is added to the **Output Template Description** list. When an input pattern will match the pattern of an incoming input stream, the defined output will be created automatically.

ZEC Network Bonding

ZEC's Network Bonding feature enables you to divide a stream into several network channels by utilizing multiple NICs and links and then subsequently reuniting them at the Zixi Broadcaster side. For example, a 5 Mbps stream can be streamed using two links, one 2 Mbps link that uses a mobile network and another 3 Mbps Wifi network. The stream is automatically bonded at the Zixi Broadcaster side without any special configuration (as long as the Push input is defined and the two NICs are setup in the machine running the Zixi Broadcaster). Network Bonding can be used for load balancing between multiple links in the following configurations:

- **ZEC with Multiple NICs to a single Zixi Broadcaster NIC** - the stream is divided at the ZEC end and then bonded at the Zixi Broadcaster end. This configuration requires configuring Network Bonding in the ZEC.
- **ZEC with Multiple NICs to multiple Zixi Broadcaster NICs** - the stream is divided at the ZEC end, sent to multiple IP addresses (each Zixi Broadcaster NIC has a separate IP address), and then bonded at the Zixi Broadcaster end. This configuration requires configuring Network Bonding in the ZEC. Each destination (i.e. each Broadcaster NIC is configured in a separate network bonding link by using a different Host IP address).
- **ZEC with single NIC to Multiple Zixi Broadcaster NICs** - the stream is sent to multiple IP addresses (each Zixi Broadcaster NIC has a separate IP address), and then bonded at the Zixi Broadcaster end. This configuration requires configuring Network Bonding in the ZEC. Each destination (i.e. each Broadcaster NIC) is configured in a separate network bonding link by using a different Host IP address.
- **ZEC with multiple NICs to another Zixi Broadcaster with a single/multiple NICs** - a Zixi Broadcaster can transfer a stream to another Zixi Broadcaster through multiple NICs at the source Broadcaster and single/multiple NICs at the destination Broadcaster. This configuration requires configuring Network Bonding in the Zixi Broadcaster.

Using Network Bonding for Hitless Failover


The Network Bonding feature can be used to ensure high availability of the stream. The feature ensures hit-less failover between multiple networks and network cards (i.e. network and hardware protection). As part of the configuration of the network bonding feature it is possible to set a NIC (which may be connected to a separate network) as a "Backup". In this case, the backup link will only be utilized if the stream has used all other available capacity. For example, a stream can be configured to be transferred on a WiFi network as the main link and a mobile network as a backup. If the WiFi link is compromised (either completely unavailable or limited bandwidth), the stream will be transferred, in full or partially through the backup mobile link and then bonded at the ZEC end, enabling uninterrupted streaming and high availability.

ZEC Output with Network Bonding

ZEC can push a stream to another ZEC instance that has been divided into multiple network channels by utilizing multiple NICs. The ZEC at the destination will subsequently be reuniting them into a single input stream.

➔ To add network bonding to a Push Output:

1. Create a **Push Output**, by following the instructions in the [Adding Push Outputs](#) section.
2. In the **Output Parameters** section, select the **Bond Links** checkbox.



The screenshot shows the 'Output parameters' dialog box. Under the 'Links' section, there is a table with columns: Host, Port, IP, Max. Bitrate [kbps], and Backup. The first row has '2088' in the Port column, 'Any' in the IP column, and 'Unlimited' in the Max. Bitrate column. Below the table, the 'Bond Links:' checkbox is checked.

Host	Port	IP	Max. Bitrate [kbps]	Backup
	2088	Any	Unlimited	<input type="checkbox"/>

Bond Links:

3. In the **Links** section, click the **+** button to add a second link:



The screenshot shows the 'Output parameters' dialog box with two links added to the table. The 'Bond Links:' checkbox remains checked.


Host	Port	IP	Max. Bitrate [kbps]	Backup
	2088	Any	Unlimited	<input type="checkbox"/>
	2088	Any	Unlimited	<input type="checkbox"/>

Bond Links:

4. In the **Host** field, type the IP address of the destination ZEC.
5. In the **Port** field, type the destination port number of the ZEC to which you want to stream. Default: 2088
6. In the **IP** field, select the NIC in the ZEC (source) that you want to use to stream.
7. In the **Max. Bitrate** field, do one of the following:
 - If you want to limit the bitrate that will be used in this link, enter the limit value in Kbps.
 - If you DO NOT want to limit the bitrate, leave the default value - "Unlimited".
8. In the **Backup** field, do one of the following:
 - If you want to use this link only if there is not enough bandwidth in the other links, select the Backup checkbox.
 - If you want to use this link in parallel to other links, DO NOT select the Backup checkbox.
9. Configure additional parameters as required.
10. Click **OK** to save the ZEC Output.

Adaptive Groups

ZEC features the ability to create multiple bitrate profiles for a single input stream and set it as an adaptive group that can be used by a supporting client. The client will automatically switch between the various bitrate profiles of the stream according to the network conditions during playback.

After creating a group with different bitrates you can test them all out by playing them with the different 3rd party players (via the  Actions menu).


You can optionally create adaptive group templates that will automatically group streams in adaptive groups instead of defining groups in advance.

Creating New Adaptive Groups

➔ To Create a New Adaptive Group:

1. In the ZEC administrative screen, click the **Adaptive** tab.
2. Click **Add Group**.

The **Adaptive live streams group** window is displayed:



Stream ID	Bitrate[kbps]
auto-created-push	3554

Protocols

Zixi HLS CMAF(DASH + fMP4 HLS)

Support MultiAudio:

Fast playback:

Convert CEA-708 to WebVTT:

HLS over multicast

HLS segment duration [secs]:

HLS segments count:

DASH segment duration [secs]:

DASH segments count:

Recording

Keep recorded files for [minutes]:

* Leave blank to use global settings.

File name template:

%G = Group Name; %N = Sequence Number; %T = Timestamp

+ Add stream OK Cancel

3. In the **Group Name** field, enter the unique string as the adaptive group's name.

Adaptive Groups

Creating New Adaptive Groups

4. Under **StreamID**, select an input stream from the drop-down list to create an adaptive bitrate.
5. Enter the desired **Bitrate[kbps]** for that stream in the adjacent field to **Stream ID**.
6. Click to add as many streams as you want to include in the group and repeat steps 4 and 5 for every stream that is added to the group.
7. Select one or more **Protocols** that will be supported for this adaptive group. The Zixi protocol option enables devices using the ZEC SDK to view the stream using the Zixi protocol.
8. Select **Support MultiAudio** if the input streams include multiple audio channels to enable multiple separate audio channels in the adaptive group.
9. Specify the HLS/Dash segment/chunk duration and count (See details in the table below).
10. Specify the duration to **Keep recorded files for [minutes]**. If the file is left as blank, the system will use the global settings, specified in the **Settings > Live Protocols** screen in the **HLS DVR Maximum Recording Duration** field.
11. In the **File name template** field, specify the file name pattern that ZEC will use to generate when saving the recorded content.
12. Click **OK**.

The new Adaptive Group is created and appears on the Adaptive screen.

Parameter	Description
Group Name	Specify the unique identifier for this group.
Stream ID	Select an input stream from the drop-down list.
Bitrate [kbps]	Specify the bitrate for the selected stream.
Protocols	Select one or more Protocols that will be supported for this adaptive group - Zixi HLS (enables devices using the ZEC SDK to view the stream using the Zixi protocol), HLS, DASH/fMP4 HLS
Support MultiAudio	Select this checkbox to enable multiple separate audio channels in the adaptive group.

Select this setting to enable low latency HLS delivery. The **Enable HLS Fast playback** on the **Settings > Live Protocols** screen must be enabled. Only the TS segments version of the HLS stream will be available for adaptive streaming, not the fragmented MP4 (fMP4) version. When enabled, the following playback URLs will be available:

Fast playback

- <http://<server url>:7777/playback.m3u8?stream=<adaptive group name>>
 - <http://<server url>:7777/<adaptive group name>.m3u8>
-
-

Adaptive Groups




Creating New Adaptive Groups

Convert CEA-708 to WebVTT	Extracts closed caption from video elementary stream and converts it to WebVTT format. This feature is currently available for HLS only and there is no support to styling/placement, just text.
HLS Over Multicast	Select this checkbox to enable multicasting of the adaptive stream (requires multicast to be enabled in the Settings)
HLS Segment Duration [sec]	Specify the duration in seconds of each segment/chunk in the HLS playlist. You can specify sub-second durations (e.g. 0.5). (Default: 6 seconds)
HLS Segments Count	Specify the number of segments in the HLS playlist.
DASH Segment Duration [sec]	Specify the duration in seconds of each segment/chunk in the DASH adaptive group. You can specify sub-second durations (e.g. 0.5). (Default: 6 seconds)
DASH Segments Count	Specify the number of segments in the DASH adaptive group.
Recording	
Keep recorded files for [minutes]	Specify the maximum time for storing the recording. If the file is left as blank, the system will use the global settings specified in the Settings > Live Protocols screen in the HLS DVR Maximum Recording Duration field.
File name template	<p>Specify the file name pattern that Zixi will use to generate when saving the recorded content. A separate file will be generated for each recording up to the time specified in the Max recorded file duration parameter (see above). After this duration a new file will be generated.</p> <p>The file name pattern can include any string and up to three variables listed below. Only the %T=HH.MM.SS Timestamp is mandatory. You can change the order of these variables and add text as long as you maintain the legitimate structure of the file in Linux and Windows:</p> <ul style="list-style-type: none">%G = Group Name – optional%N = Sequence Number – optional%T=HH.MM.SS Timestamp - mandatory

Adding Streams to Existing Adaptive Groups

You can add additional streams to existing adaptive groups.


➔ To Add Streams to an Adaptive Group:


1. In the ZEC administrative screen, click the **Adaptive** tab.
2. Select the Group to which you want to add a stream, and click  button, and then **Edit**. The **Adaptive live streams group** window is displayed.
3. Click  button for as many streams as you want to include in the group. Another Stream row will be added in the above table to which a desired **Bitrate** must be specified. When clicking on the red  at the end of any of the stream rows, the stream will be deleted from the group.
4. Click **OK**. The group has been modified accordingly.

Adaptive Groups Templates

Instead of defining adaptive groups in advance and then relating specific input streams to these groups, you can define templates with rules for automatic grouping of streams in adaptive groups. Every time a new input stream, which matches the conditions of the template, is added, it will be automatically added to the adaptive group that was defined in the template. Specific streams are identified by naming patterns and added to the group by setting static naming patterns and bitrates or dynamic patterns.

➔ To create a new adaptive group template:

1. Click the **Adaptive** tab at the top of the ZEC administrative screen.
2. In the Menu bar, click the **Templates** () button.
The Adaptive Groups Templates screen is displayed:



Adaptive Groups

Adaptive Groups Templates

3. Click the + button.

The **Adaptive Group Template** window is displayed:

Adaptive group template [X]

Input ID Pattern will be matched against inputs.
Parts of input stream ids can be assigned to variables ["\$1" .. "\$9"].
* can be used as wild card.
e.g. \$1_stream_profile_*

Input ID Pattern:

Adaptive Group Name:

Variables from Input ID pattern can be used to form adaptive group name.
e.g. \$1_adaptive_stream

Adaptive group properties

Zixi HLS DASH

HLS over multicast

Record

Keep recorded files for [minutes]:

* Leave blank to use global settings.

File name template:

%G = Group Name; %N = Sequence Number; %T = Timestamp

Adaptive group stream patterns

Streams expected in adaptive group may connect later.

Dynamic streams acquisition Static streams set

Stream pattern Bitrate [kbps]

Apply Close

4. In the **Input ID Pattern** field, enter a pattern for the Stream ID of the input stream that will be automatically added to newly created adaptive group. This pattern will be used to identify the input stream and can include variables that are marked with the "\$" sign followed by a number (e.g. \$1, \$2, etc.) and/or with an asterisk "*" wildcard. The patterns should also include a part of the string that requires an exact match. For example, the pattern "\$1_stream_\$2kbps" will match an input stream "talk_show_stream_600kbps". String parts that were matched against \$X variables, can be reused in other settings, however, string parts that were matched against an asterisk wildcard cannot be reused in other settings.
5. In the **Adaptive Group Name** field, enter a string that will be used as the name of the adaptive group. You can use the \$X variables that were used in the Input ID Pattern field above. For example, based on the above example, if you write "\$1_group", the group name will be "talk_show_group".
6. Under the **Adaptive Group Properties**, select the checkboxes of the protocols with which these streams will be transmitted (Zixi, HLS, DASH, HLS over multicast).
7. If you want to record an HLS stream, select the **Record** checkbox and in the **Keep recorded files for [minutes]**, specify the maximum time (in minutes) to record. Default:

Adaptive Groups

Adaptive Groups Templates

the time defined in the global settings, specified in the **Settings > Live Protocols** screen in the **HLS DVR Maximum Recording Duration** field.

- Under **Adaptive Group Stream Patterns**, select the method in which the streams in the adaptive group will be created:
 - Dynamic Streams Acquisition:** this method will automatically add input streams that match the defined **Input ID Pattern** and give them a bitrate value based on the **Bitrate Pattern**. This option is based on the assumption that the bitrate value is part of the input stream's ID. Based on the example above, by entering the value "\$2" in the **Bitrate Pattern** field, the system will automatically add the incoming "talk_show_stream_600kbps" stream, while giving it a 600 Kbps Bitrate setting (according to the definition in the **Input ID Pattern** field, the \$2 was assigned a value of 600kps). If another stream that matches the input ID patterns comes in (e.g. talk_show_stream_700kbps") with a different bitrate, for example, 700kbps, this stream will be also added to the same adaptive groups, however the bitrate setting will be 700 kbps.

Adaptive group stream patterns
Streams expected in adaptive group may connect later.

Dynamic streams acquisition Static streams set

Any stream matching 'Input ID Pattern' will be added.

Bitrate pattern:

To add a Dynamic Streams Acquisition bitrate pattern:

- In the **Bitrate Pattern** field add the pattern as described above.
- Click **Apply**.

The new template is added to the **Adaptive Groups Templates** list:

Adaptive groups templates [X]

Input ID Pattern	Adaptive Group Name	
\$1_stream_\$2kbps	\$1_adaptive_stream	[Edit] [Delete]

[Close]

- Static Stream Set:** if the input streams do not have the bitrate value in their ID names, you can manually define the ID and the bitrate for each stream that will be included in the group. You can define streams that are not currently connected, but will be connected at a later stage.

Adaptive Groups

Adaptive Groups Templates

Adaptive group stream patterns
Streams expected in adaptive group may connect later.

Dynamic streams acquisition Static streams set

Stream pattern	Bitrate [kbps]	
<input type="text" value="comedy_HD"/>	<input type="text" value="512"/>	<input type="button" value="+"/>
		<input type="button" value="x"/>

To add a Static Steam Set:

1. Click the + button
2. In the **Stream Pattern** field, enter a pattern for the stream ID (you can use the variables used in the Input ID Pattern field and add additional variables as needed). This pattern will be used to identify the stream and add it to the group (e.g. "comedy_HD").
3. In the **Bitrate [Kbps]** field, enter the Bitrate value of the stream.
4. Click the + button for as many streams as you want to include in the group and repeat the steps above for every stream that is added to the group.
5. Click **Apply** to save all changes.

The new template is added to the **Adaptive Groups Templates** list:

Adaptive groups templates		
Input ID Pattern	Adaptive Group Name	<input type="button" value="+"/>
<input type="text" value="\$1_stream_\$2kbps"/>	<input type="text" value="\$1_adaptive_stream"/>	<input type="button" value="edit"/> <input type="button" value="x"/>



the group will be active only when all the streams defined will be connected.


Performing Actions on Adaptive Groups

Every adaptive group has a shortcut button that can be used to perform relevant actions.

Stopping/Starting an Adaptive Group


You can start or stop the stream(s) in the adaptive group at any time.

➔ To Stop/Start the Adaptive Group:

1. In the ZEC **Adaptive Groups** page, click the adaptive group row that you want to start/stop.
2. Click the  button on the right end of the selected row and select **Start/Stop**. The status will change to Connected/Stopped accordingly.


Editing an Existing Adaptive Group


➔ To Edit the Configuration of an Adaptive Group:

1. In the ZEC **Adaptive Groups** page, click the adaptive group row that you want to edit.
2. Click the  button on the right end of the selected row and select **Edit**. The Adaptive live stream group screen is displayed. You can modify any of the settings.
3. Click **OK**. The new settings will take effect.

Deleting an Adaptive Group

➔ To delete an Adaptive Group:


1. In the ZEC **Adaptive Groups** page, click the adaptive group row that you want to delete.
2. Click the  button on the right end of the selected row, and select **Edit**. The message "**Are you sure you want to delete group <group_name>?**" is displayed.



3. Click **OK**. The selected row adaptive group will be deleted.

Record an Adaptive Group


➔ To record an Adaptive Group:


1. In the ZEC **Adaptive Groups** page, click the adaptive group row that you want to record.
2. Click the  button on the right end of the selected row and select **Record**.
A small red dot appears in the green circle at the left-hand side of the selected row indicating that adaptive group is being recorded.
3. Clicking **Stop Recording** will stop the recording of the adaptive group, and the newly recorded file will appear in the designated file directory in the **VOD** page.

Play Dash

ZEC can generate links to play the Adaptive Group stream in MPEG DASH format.

➔ To Play MPEG DASH:

1. In the ZEC **Adaptive Groups** page, click the adaptive group row that you want to playback.
2. Click the  button on the right end of the selected row and select **Play Dash**.
The following window is displayed:



3. Do one of the following:
 - If you have a locally installed MPEG DASH compatible player - click the link to stream the data to your player.
 - If you DO NOT have a player - click **Play from server**. The stream will open in a web-based player.
4. Click **Close** when finished.


Adaptive Groups


Performing Actions on Adaptive Groups

Play fMP4

ZEC can generate links to play the Adaptive Group stream in fMP4 HLS format.

➔ To Play fMP4 HLS:

1. In the ZEC **Adaptive Groups** page, click the adaptive group row that you want to playback.
2. Click the  button on the right end of the selected row and select **Play fMP4**. The following window is displayed:




3. Copy the link that is generated at the bottom of the window and paste it into a player/browser for playback.
4. Click **Close** when finished.

Play HLS


ZEC can generate links to play the Adaptive Group stream in HLS format over HTTP, UDP, or Multicast (requires Multicast enabled).

➔ To Play HLS:

1. In the ZEC Adaptive Groups page, click the adaptive group row that you want to playback.
2. Click the  button on the right end of the selected row and select Play HLS. The following window is displayed:

Adaptive Groups

Performing Actions on Adaptive Groups



The screenshot shows a dialog box titled "Link description" with a close button (X) in the top right corner. The dialog is titled "HLS" and contains the following options:

- HLS over HTTP HLS over UDP HLS over Multicast
- Live DVR
- HTTPS HTTP Fallback

Below the options is a text field containing the URL: <http://10.7.0.78:7777/adaptive1.m3u8>. At the bottom right of the dialog is a "Close" button.

3. Do one of the following:
 - **HLS over HTTP** - streams the adaptive stream over HTTP. Select **Live** to stream a live stream or select **DVR** to select a recorded stream. To stream from an encrypted HTTPS link, select the **HTTPS** checkbox. To stream from a secondary/backup server, select the **HTTP Fallback** checkbox.
 - **HLS over UDP** - streams the adaptive stream over UDP. Select **Live** to stream a live stream or select **DVR** to select a recorded stream. To stream from an encrypted HTTPS link, select the **HTTPS** checkbox. To stream from a secondary/backup server, select the **HTTP Fallback** checkbox.
 - **HLS over Multicast** - streams the adaptive stream over UDP. Select **Live** to stream a live stream or select **DVR** to select a recorded stream. To stream from an encrypted HTTPS link, select the **HTTPS** checkbox. To stream from a secondary/backup server, select the **HTTP Fallback** checkbox.
5. Copy the link that is generated at the bottom of the window and paste it into a player/browser for playback.
6. Click **Close** when finished.

Adaptive Groups


Performing Actions on Adaptive Groups

Set Preroll

A preroll transport stream file is a video/audio file that is played before the adaptive group video is played. Before setting the preroll, you should make sure that the file is available for VOD and that VOD is enabled in the File Transfer and VOD settings.

➔ To set a Pre-roll:

1. Upload the Pre-roll TS File to the designated Root folder on the ZEC server. To find your Root folder location, go to Settings > General. The Root path is specified in the Root Folder field.



Enable read only user:

Enable HTTPS administration:

Root folder: C:/Program Files\Zixi\Broadcaster\files

Max disk quota [%]: 85

2. In the **Settings > File Transfer & VOD** screen, select the **VOD** checkbox. The following window is displayed:




HLS Indexing:

MPEG-DASH Indexing:


VOD:

Encrypt downloads:

Max download speed [kbps]: 100000 ~100.0 Mbit/s

3. In the ZEC Adaptive Groups screen, click the desired adaptive group for which you want to add the preroll.
4. Click the  button on the selected row and then click **Set Preroll**.

The following window is displayed:



Preroll File Selection

Group ID:

Preroll File:

Set an empty preroll file in order to remove a group

5. In the **Group ID** field, select the adaptive group for which you want to add the preroll.
6. In the **Preroll File** field, click the **Browse** button and select the desired file.
7. Click **OK**.

Server Settings

ZEC is pre-configured with default settings, so generally there is no need to change the server settings. However, some users may want to change specific settings to meet their specific needs.

General

The General Settings screen includes basic configuration parameters for the server including the server’s ID, access ports, authorizations, security, and storage.

Field	Description
General	
ID	The unique (alphanumeric) name of the ZEC server. Typically: host name. This field is editable.

Server Settings

General

Machine local time	Shows the current time for the machine.
Web Server Port	The port number of the web server administration. You can configure this parameter to any legal port number which is supported by your Firewall. Default: 4444
Admin User Name	The user name of the administrator. The administrator is authorized to modify all parameters in the system as well as manage all the outputs and inputs on the server.
Admin Password	The password of the administrator.
Enable read / write user - except for settings screen	Select this checkbox to enable an "Operator" user. This type of user can read and write throughout all of the screens, except for the screens under the Settings menu. You can modify the user name (i.e. enter another name instead of Operator) and password.
Enable read-only user +ability to switch streams	Select this checkbox to enable a "User" user. This type of user can read throughout all of the screens as well as the ability to switch between existing streams. You can modify the user name (i.e. enter another name instead of User) and password.
Username	The account Username.
Password	The account password.
Enable read only user	Select this checkbox to enable an "Observer" user. This type of user can read throughout all of the screens. You can modify the user name (i.e. enter another name instead of Observer) and password.
Enable HTTPS administration	Enables secure HTTPS connection to the server for administration. Enabling HTTPS requires the relevant certificates and private keys. To enable HTTPS, click on the checkbox and upload the required files.
Root folder	Displays the configured root folder. You can modify the root folder by modifying the broadcaster-info.xml, which is located in the ZEC installation folder (<ZEC_Installation_Folder>\Zixi\Broadcaster\)
TR101 analyzer mode	Select the mode in which the TR101 analyzer will operate: None – no TR101 analysis ATSC – based on the Advanced Television Systems Committee recommendations. DVB – based on the Digital Video Broadcasting specifications.
Enable audio levels in matrix	Select this option to enable audio in Matrix view. When not selected the audio will be turned off.

Server Settings

General

Count per-PID statistics on push/pull inputs	Select this checkbox to enable gathering statistics on a per-PID basis for push/pull inputs.
HTTPS certificate uploaded (for HTTPS enabled)	If no certificate has been uploaded, click Upload and navigate to the file location.
HTTPS private key uploaded (for HTTPS enabled)	If no private key has been uploaded, click Upload and navigate to the file location.
HTTPS private key passphrase (for HTTPS enabled)	Enter the Private key passphrase for your HTTPS account.
SSL Setup Status	Displays the status of the SSL certificate upload process. Incomplete – the SSL setup process is incomplete. OK – the SSL setup process is complete.

HTTPS and DTLS Streaming Certificate

Certificate uploaded (for DTLS enabled)	If no certificate has been uploaded, click Upload and navigate to the file location. Note: This is the same certificate as the HTTPS certificate.
Private key uploaded (for DTLS enabled)	If no private key has been uploaded, click Upload and navigate to the file location.
Private key passphrase (for DTLS enabled)	Enter the Private key passphrase for your DTLS account.

Input Ports

Port	The port that is used for Input streams. You can modify the port number and/or add additional ports by adding a “,” between them. Adding additional ports may be necessary when there is a chance that the ISP will block a certain port. Click '+' to add additional ports. Default: 2088
IP	Enter an IP address. The default enables Any IP address.
DTLS	Click the DTLS check box to activate DTLS automatic encryption of the streams.
+ (add ports)	Click + to add additional ports.

Server Settings

General

Note: For each port you can select whether or not to activate DTLS encryption. This enables streaming of non-encrypted streams on one port and encrypted streams on a separate port.

Output Ports

Port

The port that is used for the Output streams. Displays the Output port(s). You can modify the port number and/or add additional ports by adding a “,” between them. Adding additional ports may be necessary when there is a chance that the ISP will block a certain port. Click '+' to add additional ports.

Default: 2077

IP

Enter an IP address. The default enables **Any** IP address.

DTLS

Click the DTLS check box to activate DTLS automatic encryption of the streams.

+ (add ports)

Click + to add additional ports.

Note: For each port you can select whether or not to activate DTLS encryption. This enables streaming of non-encrypted streams on one port and encrypted streams on a separate port.

MMT Ports

Port

The port that is used for the Output streams. Displays the Output port(s). You can modify the port number and/or add additional ports by adding a “,” between them. Adding additional ports may be necessary when there is a chance that the ISP will block a certain port. Click '+' to add additional ports.

Default: 2077

IP

Enter an IP address. The default enables **Any** IP address.

DTLS

Click the DTLS check box to activate DTLS automatic encryption of the streams.

+ (add ports)

Click + to add additional ports.

Note: For each port you can select whether or not to activate DTLS encryption. This enables streaming of non-encrypted streams on one port and encrypted streams on a separate port.

Limits

Select to configure thresholds for generating an alarm.

CPU [%]

The CPU utilization threshold. If this limit is exceeded, the CPU indicator at the top of the screen will appear in red, and an alarm will be generated in the event log.

Default: 90

Memory [%]

The memory utilization threshold. If this limit is exceeded, the Memory indicator at the top of the screen will appear in red, and an alarm will be generated in the event log

Default: 90

Server Settings

General

Max Disk Quota [%] The maximal percentage of the disk capacity that can be used. Default: 85

GPU [%] The GPU utilization threshold. If this limit is exceeded, the GPU indicator at the top of the screen will appear in red, and an alarm will be generated in the event log.
Default: 0

Input Bandwidth [kbps] Bandwidth utilization threshold for input streams.
Default: Unlimited.

Output Bandwidth [kbps] Bandwidth utilization threshold for output streams.
Default: Unlimited.

Server Settings

Network

Network

The Network screen enables the configuration of the network settings of the ZEC. The screen includes the option to configuration multiple NICs, VLANs, and multiple DNS Servers.

The screenshot shows the 'Settings' page with a navigation menu on the left containing: General, Network, Time, Live Protocols, Multicast Pull Outputs, VOD, ZEN Master, SSH Connections, Authorization, and Logging. The 'Network Settings' section is active, showing configuration for the 'eth0' interface. Parameters include Speed, Duplex (Full), and MTU (9001). There is a 'Custom link setting' checkbox. The 'Addresses' table shows one entry with IP 172.31.38.87, Mask 255.255.240.0, Gateway 172.31.32.1, DHCP Yes, and VLAN No. The 'DNS Servers' section has a checked 'Use DHCP DNS settings' option, with DNS1 set to 172.31.0.2 and DNS2 empty. Buttons for 'Export', 'Import', 'Delete Settings', 'Statistics', 'Routes', and 'Apply' are visible.


Field	Description
Network Settings	
eth0	Click to configure the specified NIC. Displays the following parameters: <ul style="list-style-type: none">• Speed – the network card speed• Duplex – whether the network card is full-duplex or half-duplex• MTU - the size of the largest protocol data unit (PDU) that can be communicated in a single network layer transaction.
Custom link settings	Select this checkbox to configure different link settings than the default settings.
Addresses	Displays the current IP address that is configured for the link. You edit these settings by clicking the Edit (pencil icon) button. Click the '+' button to add another link.
DNS Servers	
Use DHCP DNS settings	Select this option to use the DHCP settings instead of the DNS. If not selected, configure at least one DNS server.

➔ To Display Network Statistics:

1. From the **Settings** page of the ZEC, click **Network** on the left-hand side. The various Network settings are displayed.

Server Settings

Network

- Click  on the right-hand side.
The **UDP statistics** window is displayed.

Field	Description
UdpInDatagrams	The total number of UDP datagrams delivered.
UdpNoPorts	The total number of received UDP datagrams for which there was no application at the destination port.
UdpOutDatagrams	The total number of UDP datagrams sent from this entity.
UdpIgnoredMulti	Used in UDP multicast.
Udp6OutDatagrams	The total number of UDP6 datagrams sent from this entity.

- Click the **Refresh** button to update the data or **Close** to close the window.

Server Settings

Time

Time

The Time screen enables the configuration of the system time synchronization for the system. The time can be synchronized with the machine local time or to an external NTP server.

Settings

Export Import Delete Settings

General
Network
Time
Live Protocols
Multicast Pull Outputs

NTP settings

Machine time
2022-10-24 09:31:05 UTC Set Machine local time: 2022-10-24 09:31:05

Service: Off

NTP Servers
Host Refresh Apply +

Field	Description
NTP Settings	
Machine Time	Displays the current machine local time. To set the time click Set and modify the values.
Service	
NTP Servers	Configure external NTP servers for time synchronization. Click the + button to add an NTP server and specify the Host IP address.

Live Protocols

The Live Protocols screen enables the configuration of the HTTP/HTTPS/RTMP/WebSocket server that will broadcast the streams using live streaming protocols, particularly for adaptive streaming and internet protocols.

Field	Description
HTTP Server	
HTTP/HTTPS Server Public IP	Override the ZEC IP (e.g. download.Zixi.com) with a public IP.
Enable HTTP Server	Enable a non-secure connection over HTTP.
HTTP Server Port	Defines the HTTP Server Port. Default:7777

Server Settings

Live Protocols

Enable HTTPS Server	Enable a secure connection over HTTPS.
HTTPS Server Port	Defined the HTTPS server port. Default: 443
HTTPS certificate uploaded (for HTTPS enabled)	If no certificate has been uploaded, click Upload and navigate to the file location.
HTTPS private key uploaded (for HTTPS enabled)	If no private key has been uploaded, click Upload and navigate to the file location.
HTTPS private key passphrase (for HTTPS enabled)	Enter the Private key passphrase for your HTTPS account.
	Displays the status of the SSL certificate upload process.
SSL Setup Status	Incomplete – the SSL setup process is incomplete. OK – the SSL setup process is complete.
Enable WebSocket server	Select checkbox to enable the WebSocket server. The WebSocket server uses the WebSocket protocol to stream content. The WebSocket protocol provides full-duplex communication channels over a single TCP connection.
WebSocket Server Port	If you have enabled WebSocket, enter a dedicated port for WebSocket. (Default: 8100)
Enable FLV	Enable the streaming via the FLV protocol.
Enable HLS	Enable the streaming via the HLS protocol.
Enable CMAF (DASH + fMP4 HLS)	Enable the streaming via the CMAF protocol.
Enable SHOUTcast	Enable the streaming via the SHOUTcast protocol.
Enable HLS Fast playback	Enables low latency HLS and DASH. When this setting is enabled, all input streams on the ZEC will be published to the origin server as HLS streams, so only enable this feature if it will be actually used.
Sub GOP HLS Fast playback	Select this option to enable publishing of HLS chunk before the response is complete. This means that ZEC will start sending the HTTP response as chunks of data when they are ready before the complete response is available.

Server Settings

Live Protocols

HLS DVR maximum

recording duration Defines the maximum recording duration for HLS DVR. Default: 24 hours.
[HH:MM]:

Allow Automatic HTTP Push input Automatically creates an HTTP Push input without the need to define it in the Input screen.

Allow Automatic HTTP Pull output Automatically creates an HTTP Pull output without the need to define it in the Output screen. This works in tandem with ZEC Remote HTTP Pull Output setting, which enables sending a Zixi-protected stream to ZEC and then ZEC automatically outputs the stream as HTTP Pull) and SDK (which includes a `zixi_http_pull_out_config` option). By enabling this option, the HTTP Pull streams will be automatically created as they arrive into ZEC and displayed in the Output screen.

RTMP Server

Enable RTMP Server Enables ZEC to handle incoming RTMP streams.

RTMP Server Port The port through which the RTMP stream will be transmitted. Default: 1935

Allow Automatic RTMP Input Automatically creates an RTMP input without the need to define it in the Input screen.

Allow Automatic RTMP Output Automatically creates an RTMP output without the need to define it in the Output screen. This works in tandem with ZEC **Remote RTMP Output** setting, which enables sending a Zixi-protected stream to ZEC and then ZEC automatically outputs the stream as RTMP) and SDK (which includes a `zixi_rtmp_out_config` option). By enabling this option, the RTMP streams will be automatically created as they arrive into EC and displayed in the Output screen.

Multicast Pull Outputs

Multicast pool is a collection of multicast IP addresses that automatically assign a multicast IP when an input is being pulled out of ZEC. When the “multicast pool” setting is enabled, you do not have to define a specific multicast IP address for every push stream. Instead, you simply enable the Multicast Only parameter and ZEC will assign the multicast IP automatically when it pulls the stream out. When the multicast stream is connected, it will appear in the Status table at the bottom of the screen.

The screenshot shows the 'Settings' page for 'Multicast Pull Outputs'. The top navigation bar includes 'STATUS', 'INPUTS', 'OUTPUTS', 'ADAPTIVE', 'VOD', 'SETTINGS', 'EVENT LOG', 'MATRIX', and 'LOGOUT'. The 'Settings' page has a sidebar with options: General, Network, Time, Live Protocols, Multicast Pull Outputs (selected), VOD, ZEN Master, SSH Connections, and Authorization. The main configuration area includes: 'Allow' (checkbox), 'Multicast pool address range' (text input: 225.5.0.0/16), 'Port' (text input: 5000), 'NIC' (dropdown: Any), and 'TTL' (text input: 1). Below the configuration is a 'Status' table with columns: Stream, IP, Multicast, and Unicast. The table is currently empty with the message 'No data available in table'.


Field	Description
Configuration	
Enabled	Enables multicast pool
Address	Specify the range of IP addresses (CIDR format).
Port	Specify the port that will be shared by all of the members of the pool.
NIC	Specify the network card to use for the outgoing multicast traffic.
TTL	Specify the Time To Live.

Zen Master

To connect the ZEC to ZEN Master, you will need to create a reverse SSH tunnel by following the instructions displayed in ZEN Master within the **Configuration** tab of the relevant ZEC.

➔ To connect the current ZEC to ZEN Master:

1. In Zen Master, on the main menu, click Zixi Edge Devices.
2. Select the relevant ZEC device.
3. Click the Configuration tab and follow the instructions displayed in this tab.




SSH Connections

SSH (Secure Shell) is a network protocol that allows a secure access over an encrypted connection. Reverse SSH is a technique that can be used to access systems (that are behind a firewall) from the outside world. As part of the SSH configuration, you can configure a connection to the server and then configure any number of SSH tunnels to the same server.

➔ To create an SSH connection to a server:


1. Click the **Add Connection** button.



2. In the **Host** field, enter the IP address or host name of the host that you wish to access.
3. In the **Port** field, enter the port number to access the host.
4. Click **Apply**.
The connection to the specified server is configured.

➔ To create a reverse tunnel to the same server:

1. Under the destination that you have configured, click **Edit Credentials**.



The **Connection Credentials** dialog appears.

2. In the **User** field, enter the user name to access the tunnel.
3. Click **Private Key**, navigate to the file location and select the file.
4. Click **Apply**.

Server Settings

SSH Connections

5. Click **Add** to add a reverse tunnel.

The screenshot shows the 'SSH Connections' interface. It has a header 'SSH Connections' and a sub-section 'Defined Connections'. Under 'Defined Connections', there is a connection for 'zixi.devcloud.zixi.com' with a destination of 'zixi.devcloud.zixi.com:22'. Below this, there is a 'Reverse Tunnels' section with a table. The table has columns for 'Remote Source Port', 'Local Destination IP', 'Local Destination Port', and 'Status'. An 'Add' button is highlighted with a red box in the bottom right corner of the table. There are also buttons for '+ Add connection', 'Edit', 'Delete', and 'Edit Credentials'.


Remote Source Port	Local Destination IP	Local Destination Port	Status

The **Tunnel details** dialog appears.

6. In the **Remote Source Port** field, enter the port number of the remote server.
7. In the **Local Destination IP** field, enter the IP address of the local server.
8. In the **Local Destination Port** field, enter the port number to connect the tunnel.
9. Click **OK**.
10. Repeat steps 5-9 to add additional tunnels.

Authorization

Authorization can be configured for any incoming or outgoing streams.



Field	Description
Authorization	

None (default) - authorization will be defined in the Input and Output streams. In this case you will need to define the password in the Input and the Output streams. Unless you select the Allow automatic push inputs and/or Allow automatic pull outputs checkboxes (as described below).

Text File – this option manages authorizations in a text file. This option is useful for large OTT operations, as it does not require configuration for every user. The text file contains pairs of stream name and password that are used for the input streams. For the outputs, it contains the stream name, user and password of the viewer.

Linux Users – uses the built-in authorization of the Linux operating system.

Global Password – a single password that will be used for all access requests.

Users Files -

HTTP Server – ZEC will generate an HTTP request to an external server on every connection.

Stream access – access authorization on the stream level. The password needs to be the same as the password to access the stream.

Windows Users – uses the built-in authorization of the Windows operating system. Other override authorization techniques are available. For more information contact Zixi support

Parameter Specify the password that you would like to use for access

Allow Automatic Push inputs If this checkbox is selected, the ZEC will automatically create an input stream each time it receives a push stream from a source.

Server Settings

Authorization

However, if this checkbox is not selected, only predefined Push Input streams with the defined credentials will be allowed in (this is the default setting and the behavior in previous versions).

Default: not selected.

Allow Automatic pull outputs

If this checkbox is selected, any ZEC that requests a Pull output will be granted access. In this case, a Pull output will be automatically created in ZEC (this is the default setting and the behavior in previous versions).

However, if this checkbox is not selected, only predefined Pull output streams with the defined credentials will be pulled by ZEC.

Default: selected.

Separate user folders

Select this checkbox to enable access by user folders

Logging

Select the checkbox to enable logging of the connections

Logging

The Logging screen defines the logs location and preferences for debugging purposes.

The screenshot shows a web interface with a navigation bar at the top containing 'STATUS', 'INPUTS', 'OUTPUTS', 'ADAPTIVE', 'VOD', 'SETTINGS', 'EVENT LOG', and 'MATRIX'. The 'SETTINGS' tab is active. Below the navigation bar, there are buttons for 'Export', 'Import', and 'Delete Settings'. The main content area is titled 'Logging' and contains the following settings:

- General level: None (dropdown menu)
- Path: (text input field)
- Max log files: 3 (text input field)
- Max log file size [MB]: 1024 (text input field)
- Send crash reports: (checkbox)
- Apply (button)

A sidebar on the left lists various settings categories: General, Network, Time, Live Protocols, Multicast Pull Outputs, VOD, ZEN Master, SSH Connections, Authorization, and Logging (which is highlighted).

Field	Description
Logging	
General Level	The Severity Level that will be collected in the log, from Info, Warning, Error, to Fatal. Selection of lower severity levels will include all higher-level logs. Default: None, since Logging is resource-intensive and only enabled when necessary.
Path	The log file name and path where the collected event information will be stored.
Max log files	The maximal number of log files.
Max log file size (MB)	The maximal size of each log file.
Send crash reports	Select the checkbox to send a crash report to Zixi Support.

ASI

The ASI screen is used to configure the ASI interface when there is an ASI card in the machine. You can use this screen to reverse the direction of the ports on the ASI card. The port numbers should correspond to the port numbers on your ASI card.

ASI Settings

Available ports

#	Name	Data direction	
1	Port 1	Input	→ Reset to output
2	Port 2	Input	→ Reset to output
3	Port 3	Output	← Reset to input
4	Port 4	Output	← Reset to input

ASI output stuffing:
 ASI output PLL:
 ASI fix time:
 Initial buffer time[ms]:
 Read buffer size[B]:

[Apply](#)

Field	Description
ASI output stuffing	Select this checkbox to achieve CBR (constant bitrate) by padding the ASI stream with TS null packets.
ASI output PLL	Select this checkbox to enable a phase-locked loop. A phase-locked loop or phase lock loop (PLL) is a control system that generates an output signal whose phase is related to the phase of an input signal. When selecting this option, the system will adjust the bitrate that is sent according to the fullness rate of the output buffer.
ASI fix time	Select this checkbox to adjust input timestamps to local machine time.
Initial buffer time [ms]	To avoid underflows, specify the output buffer size that will be filled before starting the transmission.
Read buffer size [B]	Specify the input read buffer to fill, before passing data to the application. Larger buffer size should be specified for higher bitrates; Smaller buffer size will be more responsive and smoother in lower bitrate streams.

Reversing the directions of the ports

➔ To Reverse the Direction of the Ports:

1. From the **Settings** page of the ZEC, click **ASI** on the left-hand side. The various **ASI settings** are displayed.

The screenshot shows the 'ASI Settings' interface. At the top, there is a section titled 'Available ports' containing a table with four rows. Each row has columns for '#', 'Name', and 'Data direction', followed by a button to change the direction. Below the table are several checkboxes for 'ASI output stuffing', 'ASI output PLL', and 'ASI fix time'. There are also two input fields for 'Initial buffer time[ms]' (set to 500) and 'Read buffer size[B]' (set to 131600). An 'Apply' button is located at the bottom right of the settings area.

#	Name	Data direction	
1	Port 1	Input	→ Reset to output
2	Port 2	Input	→ Reset to output
3	Port 3	Output	← Reset to input
4	Port 4	Output	← Reset to input

ASI output stuffing:

ASI output PLL:

ASI fix time:

Initial buffer time[ms]:

Read buffer size[B]:

Apply

2. Click the desired **RESET** button to the right of the port that you want to reverse. A confirmation window is displayed with the notification that the service must first be restarted before the direction is reversed.

Field	Description
Available ports	
Name	Displays the port number used by the ASI protocol.
Data Direction	Displays the direction of the data being transmitted by the ASI protocol.

Threads

The Threads screen enables the configuration of the maximal number of concurrent CPU threads allowed for each component/service. Enter -1 to limit the threads according to the number of cores.

Field	Description
Input	Maximal number of threads for all input streams.
Output	Maximal number of threads for all output streams.
VOD	Maximal number of threads for all VOD streams.
Read	Maximal number of threads to handle Zixi Push inputs. It is recommended to adjust this value to have 1 read core per 500Mbps of push input traffic.
Pool	Maximal number of threads for managing buffer pool.
RTMP	Maximal number of threads for RTMP streams.
UDP In	Maximal number of threads for UDP input streams.
UDP Out	Maximal number of threads for Curl
HTTP In	Maximal number of threads for TS over HTTP input stream.
Transcoder	Maximal number of threads for transcoding.

Server Settings


Threads

Push Output Receive	Maximal number of threads used for Zixi Push output connections.
HTTP	Maximal number of threads for the HTTP server.
Authorization	Maximal number of threads for the authorization component.
Analyzer	Maximal number of threads for the analyzer component.
Adaptive	Maximal number of threads used to segment adaptive groups.
Various Inputs	Maximal number of threads used for all other types of inputs/outputs (e.g., HLS input, TS, TCP input, SRT inputs, ASI inputs, SRT outputs, file over http input).
Accept	Maximal number of threads used to accept Zixi Pull outputs.

Viewing Events Log

The Event Log screen displays all the events (errors, connections, configuration changes, analysis events etc.) that occurred in the ZEC. The logs are displayed in the server time (not local time) and can be exported as a .cvs file.

In Linux, the event log is written to a file located in the following location on the disk:
/log/var/messages



The screenshot shows the ZEC Event Log interface. At the top, there is a navigation bar with tabs for STATUS, INPUTS, OUTPUTS, ADAPTIVE, VOD, FILES, TRANSCODER, SETTINGS, EVENT LOG (selected), and MATRIX. A LOGOUT button is in the top right corner. Below the navigation bar, there is a search bar labeled "Event Log" with a "Search Events" input field and buttons for "Clear", "Save", "System Log", and "Refresh". The main content area is a table with two columns: "Time/Date" and "Event". The table contains 12 rows of event data.

Time/Date	Event
2022-02-16 17:46:01	Output of hls_4088 to QA-Elena-SRT-1-3wyo cleared alert Low bitrate
2022-02-16 17:45:24	Output of hls_4088 to QA-Elena-SRT-1-3wyo raised alert Low bitrate
2022-02-16 17:42:36	Output of pull to ristMainPush-pull cleared alert High bitrate
2022-02-16 17:42:33	Output of pull to srt-pull cleared alert High bitrate
2022-02-16 17:42:33	Output of pull to srt2-pull cleared alert High bitrate
2022-02-16 17:42:33	Output of pull to tcp-pull cleared alert High bitrate
2022-02-16 17:42:33	Output of pull to QA-Elena-SRT-1-3wyo cleared alert High bitrate
2022-02-16 17:42:33	Output of pull to QA-Elena-SRT-1-3wyo cleared alert High bitrate
2022-02-16 17:42:30	Output of pull to ristMainPush-pull raised alert High bitrate
2022-02-16 17:42:28	Input srt-pull cleared alert High bitrate
2022-02-16 17:42:28	Output of pull to QA-Elena-SRT-1-3wyo raised alert High bitrate
2022-02-16 17:42:28	Output of pull to QA-Elena-SRT-1-3wyo raised alert High bitrate

➔ To Clear the Log:

1. In the **Event Log** screen, click **Clear** on the upper right-hand corner. The events on the log screen are deleted.

➔ To Save the Log as a File:

1. In the **Event Log** screen, click **Save** on the upper right-hand corner. A .cvs file is created and saved to the local destination.

➔ To Refresh the Screen:

1. In the **Event Log** screen, click **Refresh** on the upper right-hand corner. The data on the screen is updated.

Using the Matrix

The Zixi Matrix view provides a visual-based alternative to managing the streams, by previewing the input and output streams with their current status. Matrix offers drag and drop capabilities to connect input streams to outputs as well as some of the actions that were covered in the Performing Actions on Input Streams and Performing Actions on Output Streams sections above.

The following formats are supported in the Matrix:

- Video:
 - MPEG 1/2, 8bit 4:2:0 , interlaced/progressive, up to 60fps, up to Full HD (1080p)
 - H.264/AVC, 8/10 bit, 4:2:0, 4:2:2, 4:4:4, interlaced/progressive, up to 60fps, up to 4k (2160p)
 - H.265/HEVC, 8/10 bit, 4:2:0, 4:2:2, 4:4:4, interlaced/progressive, up to 60fps, up to 4k (2160p)
 - JPEG2000, 8/10 bit, 4:2:0, 4:2:2, interlaced/progressive, up to 60fps, , up to 4k (2160p)
- Audio (for audio levels meter overlay):
 - AAC (LC, HEV1, HEV2)
 - AC3 (downmix to stereo)
 - Opus
 - MPEG1/2 Layer 1/2/3

Connecting Input to Output

An easier method of connecting inputs to outputs.

➡ To Connect an Input to an Output:

1. Drag the desired input thumbnail and drop it over a specific output thumbnail. The desired input is connected to the selected output.

Disconnecting Output from Input


➔ Disconnect an Input to an Output:

1. Click on the **To connected stream** that you want to disconnect.
2. Click **Unlink**. A confirmation window is displayed.
3. Click **Confirm**. The Output is disconnected from the Input.

Matrix Interface Elements

The Matrix view displays preview thumbnails of the Input and Output streams. Preview thumbnails of input streams are presented in the Inputs pane and preview thumbnails of output streams are presented in the Outputs pane.

- If the stream is active - the live video will be shown in the preview thumbnail.
- If an input stream is not active – the preview thumbnail will include an “Offline” message.
- If an output stream has been created, but has not been connected to an input – the preview thumbnail will include the following message - “Drag Input Here”.
- If a connected output stream does not receive a live stream - the preview thumbnail will include a “No Video” message.



Changing Matrix View

You can modify the size of the panes, the size of the preview thumbnails, and re-arrange the order the preview thumbnails.

➔ To modify the size of the panes:

1. Click on one of the rounded **pane size anchors** (see screenshot above)

➔ To modify the size of the preview thumbnails:


1. Click on one of the sizes in the **preview size controller** (see screenshot above).

➔ To re-arrange the order the preview thumbnails:

1. Drag and drop the preview thumbnail to the desired position within the pane.

Searching for Specific Streams

➔ To Search for a Specific Stream:

1. Type in the specific stream name in the appropriate (Input or Output) search text box on the top of the console and click .
2. The relevant stream will be the only one to be displayed in the pane.

Preview Thumbnail Elements

The following stream formats are supported for thumbnail preview:

- Scan Style: Interlaced and Progressive
- Codec: MPEG2, H.264/AVC
- Frame Size: SD, HD (720p), Full HD (1080p), 4K (2160p)
- Frame Rate: 24fps, 25fps, 29.97fps, 30fps, 59.94fps, 60fps
- Chroma Subsampling: 4:2:0
- Bit Depth: 8-bit (MPEG2, H.264/AVC), 10-bit (H.264/AVC)

Using the Matrix

Viewing Stream Details

The preview thumbnail includes the following elements:



Element	Description	Action
Status Indicator	Displays the unique identifier for this group.	
Stream ID	Displays the unique name for the stream.	
Bitrate [kbps]	Displays the bitrate of the active stream.	
Uptime	Displays the amount of time the stream has been active.	
Record	Stream recording	Click the record button to start recording. Click again to stop recording
Zoom	Opens the stream in a larger preview window with sound	Click the Zoom icon to open the larger preview screen.

Viewing Stream Details


➔ To View Stream Details:

Click anywhere on the preview thumbnail.

The Stream Details window opens:

Using the Matrix


Viewing Stream Details



Configuring Hitless Failover

ZEC features hitless failover for inputs, enabling uninterrupted streaming when switching from one source to another. The hitless failover feature is based on the SMPTE 2022-7 standard, which specifies “seamless” or hitless failover between binary-identical streams with synchronized RTP headers. ZEC’s patent-pending hitless failover technology works by comparing the transport stream payload, without relying on sequences being synchronized. ZEC then applies a proprietary sequencing algorithm to identify missing parts and fill-in missing packets.

The Hitless Failover feature is supported in the inputs of ZEC.



The hitless failover configuration involves grouping two inputs in a "Failover Group". The failover group includes the following configuration options for the merging of binary-identical streams:

The merging of the streams can be achieved using one of the following methods:

- **RTP headers (SMPTE 2022-7)** – if the sources are RTP and the RTP headers were maintained, ZEC will use the SMPTE 2022-7 to compare and merge the two streams in order to allow hitless failover. This option is the most recommended as it will use the sequence and the timestamp in the packets to compare which packets are missing. This method is more accurate than methods that compare the entire payload or methods that use sophisticated DNA sequencing algorithm, which are more error prone, as the payload may have multiple matches.
- **RTP headers or TS content** – if the sources do not have RTP headers, ZEC will try to merge using the MPEG-TS content itself.

In these cases, when one of the streams is disrupted or interrupted completely, ZEC will seamlessly use the packets of the other input without any disruptions.



If the streams are not identical, the failover process will not be seamless and may take up to a second.

A Failover Group can comprise two or more inputs. In a group of three or more, you can define one or more streams as a "Backup". In this case the system will always try to recover packets

Configuring Hitless Failover

Viewing Stream Details

from "Primary" streams first and only if there are no available primary streams, it will use the backup streams. When one of the primary streams becomes available, the system will automatically jump to the primary stream.

While the ZEC GUI only enables configuration of primary streams at a single priority level, through the ZEC API it is possible to assign different priorities as follows:

- Priority 0 – means backup. It will be used only if all other streams are unavailable.
- Priority greater than 0 - means primary.

The Failover Group has its own Stream ID, just like an Input Stream, and will appear in the Inputs list. Although the topology above shows only one ZEC instance, it is also possible to have multiple targets (e.g. two or more ZEC instances), each with its own Failover Group of inputs to enable a more complete system-level redundancy.

To configure a Failover Group, follow the instructions in the [Creating a Failover Group](#) section.

Configuring HTTPS

ZEC supports HTTPS encryption based on OpenSSL. ZEC expects certificate files in X.509 textual format (sometimes called 'pem') with a full chain of certificates, each one starts with "----BEGIN CERTIFICATE----", and the associated private key file, that starts with "----BEGIN PRIVATE KEY----". The certificate can be provided by an SSL/TLS certificate provider (Certification Authority) where the domain is registered, such as VeriSign, Digicert, etc.. Alternatively, the certificate can be self-signed. A self-signed certificate is a certificate that is signed with its own private key. Self-signed certificates can be used to encrypt data just as well as CA-signed certificates, but your users will be displayed a warning that says that the certificate is not trusted by their computer or browser. Therefore, self-signed certificates should only be used if you do not need to prove your service's identity to its users (e.g. non-production or non-public servers).

Obtaining a CA-signed Certificate

Reach out to the hosting provider for instructions on how to obtain a CA-signed HTTPS certificate. As part of this process, you will be required to generate a certificate signing request (CSR). A CSR consists mainly of the public key of a key pair, and some additional information. Both of these components are inserted into the certificate when it is signed. To learn more about generating a CSR, go to - <https://www.digitalocean.com/community/tutorials/openssl-essentials-working-with-ssl-certificates-private-keys-and-csrs>.

Creating a Self-signed Certificate

Instead of obtaining a CA-signed certificate, you can create a self-signed certificate.

You can generate self-signed x.509 certs with OpenSSL by using the following command:

```
openssl req -x509 -newkey rsa:2048 -keyout selfsigned_key.pem -out selfsigned_cert.pem
```

To learn more about generating a self-signed certificate, go to:

<https://www.digitalocean.com/community/tutorials/openssl-essentials-working-with-ssl-certificates-private-keys-and-csrs>.

Uploading the Certificate and Private Key

After obtaining a CA-signed certificate or creating a self-signed one, you will need to upload the certificate and private key to ZEC.

➡ **To upload the certificate and private key:**

1. In **ZEC UI**, go to **Settings > General**.

Configuring HTTPS

Uploading the Certificate and Private Key

2. Click **+** to expand the HTTPS and DTLS Streaming Certificate section
3. In the **Certificate Uploaded** field, click **Upload** and select the certificate file.
4. In the **Private Key Uploaded** field, click **Upload** and select the Private Key.
5. In the **Private Key Passphrase** field, type the passphrase or leave empty (Default passphrase is empty, ignore the '****').
6. Click **Apply**.
If the process was successful, the **SSL setup status** field will turn to "OK".

Configuring MultiPath TCP

Developed by the Internet Engineering Task Force's (IETF) Multipath TCP working group, MultiPath TCP (MPTCP) is an effort towards enabling the simultaneous use of several IP-addresses/interfaces by a modification of TCP that presents a regular TCP interface to applications, while in fact spreading data across several subflows. This means that the Linux Kernel should be updated to support MPTCP.

The MPTCP functionality is similar to ZEC's "multi-link bonding" feature, which is available for UDP only, while MPTCP works on TCP.

If both the sending end and the receiving end support MultiPath TCP, ZEC can use this functionality to transmit a stream over TCP using multiple network interfaces (e.g. Wifi + mobile). The multiple links can be configured to:

- **Aggregate** - aggregates the bandwidth of the multiple links in order to use the total capacity of these links. In this case ZEC will use all available bandwidth among all available flows (if needed) to send the stream.
- **Duplicate** - enhance the path's resiliency by duplicating the stream and sending through all links in order to overcome errors and packet loss.

MultiPath Modes

MultiPath TCP can be used in two modes:

- **Pull** – when pulling the stream, the receiving-end has multiple network interfaces (e.g. two NIC) while the sending side has one network interface. When the stream is pulled by the receiving-end using the MultiPath feature, the client (receiving side / puller) creates the sub-flows, (one per nic) and connects to the "source" (the server). The definition of the NICs in the destination is done automatically at the OS socket level. To configure this mode:
 - **In the sending side** - In **Settings > Live Protocols** screen, enable the **Allow automatic HTTP pull output** option. In this option the output will be created automatically when the Pull connection is established. Following the connection, the two links will be displayed as bonded links. When the connection is established, the two links will be displayed as bonded links as shown below.

Configuring MultiPath TCP

MultiPath Modes

Status	Name	Type	Destination	Bitrate[kbps]	Uptime	Latency	Input ID
Connected	HTTP_10.6.0.17314823...	HTTP	169.1.119.188:44750	1128	00:00:04	0	aaa

Status	Link	Bitrate[kbps]	Up Time
Connected	41.13.96.197:56207@10.6.0.173	0	00:00:02
Connected	169.1.119.188:52910@10.6.0.173	1180	00:00:02

- **In the receiving side** – Configure a **TS over HTTP Input as Pull**. When the connection is established, only one link is displayed as shown below.

Status	ID	Type	Source	Bitrate[kbps]	Up Time	TR 101 290	Error
Offline	aaa	File	20.ts	0	00:00:00	Off	Stopped
Connected	ts-pull	HTTP	http://52.91.24.109:7777/aaa.ts	1149	00:00:08	Off	None

- **Push** – when pushing the stream, the receiving-end has one or more network interfaces (e.g. two NICs) while the sending side can have one network interface. In this case, you should configure it in the following way:

- **In the sending side** – you will need to configure a **TCP output** from the ZEC in the sending side. In this case you can configure the two links as **Aggregate** or **Duplicate**, as described above. When the connection is established, the two links will be displayed as bonded links as shown below.


Status	Name	Type	Destination	Bitrate[kbps]	Uptime	Latency	Input ID
Stopped		UDP	10.0.0.37:10000	0	00:00:00	0	8000
Stopped		UDP	127.0.0.1:8000	0	00:00:00	0	aaa
Connected	bbb	TCP	52.91.24.109:7777	1113	00:01:18	0	aaa

Status	Link	Bitrate[kbps]	Up Time
Connected	52.91.24.109:7777@172.20.10.10	402	00:01:17
Connected	52.91.24.109:7777@10.0.0.75	1058	00:01:17

- **In the receiving side** - In the receiving-end, if this is also a ZEC, you have two options:
 - Configure a **TS over HTTP Input as Push**. In this option the Push input is ready in advance and will show the bitrates of both TCP connections when the connection has been established.
 - In **Settings > Live Protocols** screen, enable the **Allow automatic HTTP push input option**. In this option the input will be created automatically when the Push connection is established. When the connection is established, the two links will be displayed as bonded links as shown below.

Configuring MultiPath TCP

MultiPath TCP Setup



Status	ID	Type	Source	Bitrate[kbps]	Up Time	TR 101 290	Error	Outputs
Connected	bbb	* HTTP_PUSH		1182	00:01:13	Off	None	0

Links	Source	Bitrate[kbps]	Up Time
bbb-41.13.98.197	41.13.98.197	545	00:01:10
bbb-109.1.119.188	109.1.119.188	983	00:01:10

MultiPath TCP Setup

ZEC supports MultiPath TCP for Linux based on the OS Kernel support. This means that the Linux Kernel should be updated to support MPTCP.

➔ To setup MultiPath TCP:

- Follow the relevant instructions in - <https://multipath-tcp.org/pmwiki.php/Users/HowToInstallMPTCP?>

Using an External Storage


Modification of location of the ZEC 'cache' directory may be desired to minimize HDD used at the default location for recording streams. The default storage location (C:\Program Files\Zixi\Broadcaster\cache) can be replaced by using a symbolic link.




ZEC will need to be in a Maintenance Window to apply these steps as the service will be turned off and on.

➔ To configure an external storage path in windows:

1. On the ZEC Windows machine, stop the ZEC service, by going into the operating system **Services** screen.
2. Double click the ZEC service to open its configuration properties.
3. Under the **General** tab, in the **Startup type** drop-down menu, select the **Manual** option.
4. Click the **Stop** button and then click **OK**.



5. Delete the 'cache' file located at C:\Program Files\Zixi\Broadcaster\cache. This may require Administrator privileges depending on your environment.
6. On the planned new location create your new cache directory. In the example below the directory was created in d:_Zixi\Bx\cache.



7. Go into the Windows Command line (cmd) as an Administrator.
8. Enter a makelink command to create a new Symbolic link from the original path to the newly created 'cache' folder. For example:

```
mklink /D "c:\Program Files\Zixi\Broadcaster\cache" d:\_Zixi\Bx\cache
```

```
Administrator: Command Prompt
Microsoft Windows [Version 10.0.17134.885]
(c) 2018 Microsoft Corporation. All rights reserved.

C:\WINDOWS\system32>mklink /D "c:\Program Files\Zixi\Broadcaster\cache" d:\_Zixi\Bx\cache
symbolic link created for c:\Program Files\Zixi\Broadcaster\cache <=> d:\_Zixi\Bx\cache

C:\WINDOWS\system32>
```

The newly created symbolic link for cache will be displayed in the following directory -
C:\Program Files\Zixi\Broadcaster\

9. Go into the operating system **Services** screen.
 10. Double click the ZEC service to open its configuration properties.
 11. Under the **General** tab, in the **Startup type** drop-down menu, select the Automatic option.
 12. Click the **Start** button and then click **OK**.
- The recording of input streams will be stored in the new directory.

- License for OpenSSL

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit

(<http://www.openssl.org/>)

THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This product includes cryptographic software written by Eric Young (eay@cryptsoft.com). This product includes software written by Tim

Hudson (tjh@cryptsoft.com).

Copyright (c) 1998-2017 The OpenSSL Project. All rights reserved.

- License for Libssh2

Copyright (c) 2004-2007 Sara Golemon <sarag@libssh2.org>

Copyright (c) 2005,2006 Mikhail Gusarov <dottedmag@dottedmag.net>

Copyright (c) 2006-2007 The Written Word, Inc.

Copyright (c) 2007 Eli Fant <elifantu@mail.ru>

Copyright (c) 2009-2014 Daniel Stenberg

Copyright (C) 2008, 2009 Simon Josefsson

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of the copyright holder nor the names of any other contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

- License for DekTec's Linux SDK. Version 1, August 2012

Copyright (C) 2000-2015 DekTec Digital Video B.V.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

2. Redistributions in binary format must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation.

THIS SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL DEKTEC DIGITAL VIDEO BV, ITS AGENTS OR ITS EMPLOYEES BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, INCIDENTAL, OR OTHER DAMAGES (INCLUDING DAMAGES FOR THE LOSS OF USE, INFORMATION, GOODWILL, PROFIT, WORK STOPPAGE, DATA, BUSINESS OR REVENUE) UNDER ANY CIRCUMSTANCES, OR UNDER ANY LEGAL THEORY, WHETHER IN CONTRACT, IN TORT, IN NEGLIGENCE, OR OTHERWISE, ARISING FROM THE USE OF, OR INABILITY TO USE THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.